



Linux Ubuntu 26.04 Manual Pages on command 'restic-unlock.1'

\$ man restic-unlock.1

restic backup(1) restic backup(1)

NAME

restic-unlock - Remove locks other processes created

SYNOPSIS

restic unlock [flags]

DESCRIPTION

The "unlock" command removes stale locks that have been created by other restic processes.

EXIT STATUS

Exit status is 0 if the command was successful. Exit status is 1 if there was any error.

OPTIONS

-h, --help[=false] help for unlock

--remove-all[=false] remove all locks, even non-stale ones

OPTIONS INHERITED FROM PARENT COMMANDS

--cacert=[] file to load root certificates from (default: use system certificates or \$RESTIC_CACERT)

--cache-dir="" set the cache directory. (default: use system default cache directory)

--cleanup-cache[=false] auto remove old cache directories

--compression=auto compression mode (only available for repository format version 2), one of (auto|off|max) (default: \$RESTIC_COMPRESSION)

--http-user-agent="" set a http user agent for outgoing http requests

--insecure-no-password[=false] use an empty password for the repository, must be passed to every restic command (insecure)

--insecure-tls[=false] skip TLS certificate verification when connecting to the repository

tory (insecure)

`--json[=false]` set output mode to JSON for commands that support it

`--key-hint=""` key ID of key to try decrypting first (default: `$RESTIC_KEY_HINT`)

`--limit-download=0` limits downloads to a maximum rate in KiB/s. (default: unlimited)

`--limit-upload=0` limits uploads to a maximum rate in KiB/s. (default: unlimited)

`--no-cache[=false]` do not use a local cache

`--no-extra-verify[=false]` skip additional verification of data before upload (see documentation)

`--no-lock[=false]` do not lock the repository, this allows some operations on read-only repositories

`-o, --option=[]` set extended option (key=value, can be specified multiple times)

`--pack-size=0` set target pack size in MiB, created pack files may be larger (default: `$RESTIC_PACK_SIZE`)

`--password-command=""` shell command to obtain the repository password from (default: `$RESTIC_PASSWORD_COMMAND`)

`-p, --password-file=""` file to read the repository password from (default: `$RESTIC_PASSWORD_FILE`)

`-q, --quiet[=false]` do not output comprehensive progress report

`-r, --repo=""` repository to backup to or restore from (default: `$RESTIC_REPOSITORY`)

`--repository-file=""` file to read the repository location from (default: `$RESTIC_REPOSITORY_FILE`)

`--retry-lock=0s` retry to lock the repository if it is already locked, takes a value like 5m or 2h (default: no retries)

`--stuck-request-timeout=5m0s` duration after which to retry stuck requests

`--tls-client-cert=""` path to a file containing PEM encoded TLS client certificate and private key (default: `$RESTIC_TLS_CLIENT_CERT`)

`-v, --verbose[=0]` be verbose (specify multiple times or a level using `--verbose=n``, max level/times is 2)

SEE ALSO

`restic(1)`

generated by `restic generate`

Jan 2017

`restic backup(1)`