



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'Locale::RecodeData::ISO_2033_1983.3pm'

```
$ man Locale::RecodeData::ISO_2033_1983.3pm
```

```
Locale::RecodeData::ISO_2033_19UserpContributed Perl DocumeLocale::RecodeData::ISO_2033_1983(3pm)
```

NAME

```
Locale::RecodeData::ISO_2033_1983 - Conversion routines for ISO_2033_1983
```

SYNOPSIS

```
This module is internal to libintl. Do not use directly!
```

DESCRIPTION

```
This module is generated and contains the conversion tables and routines for ISO_2033-1983.
```

COMMENTS

```
The following comments have been extracted from the original charmap:
```

```
version: 1.0
```

```
repertoiremap: mnemonic,ds
```

```
source: ECMA registry
```

```
alias ISO-IR-98
```

```
alias E13B
```

```
Please note that aliases listed above are not necessarily valid!
```

CHARACTER TABLE

The following table is sorted in the same order as the original charmap. All character codes are in hexadecimal. Please read 'ISO-10646' as 'ISO-10646-UCS4'.

Local | ISO-10646 | Description

```
-----+-----+-----  
00 | 00000000 | NULL (NUL)  
01 | 00000001 | START OF HEADING (SOH)  
02 | 00000002 | START OF TEXT (STX)  
03 | 00000003 | END OF TEXT (ETX)  
04 | 00000004 | END OF TRANSMISSION (EOT)  
05 | 00000005 | ENQUIRY (ENQ)  
06 | 00000006 | ACKNOWLEDGE (ACK)  
07 | 00000007 | BELL (BEL)  
08 | 00000008 | BACKSPACE (BS)  
09 | 00000009 | CHARACTER TABULATION (HT)  
0A | 0000000A | LINE FEED (LF)  
0B | 0000000B | LINE TABULATION (VT)  
0C | 0000000C | FORM FEED (FF)  
0D | 0000000D | CARRIAGE RETURN (CR)  
0E | 0000000E | SHIFT OUT (SO)  
0F | 0000000F | SHIFT IN (SI)  
10 | 00000010 | DATALINK ESCAPE (DLE)  
11 | 00000011 | DEVICE CONTROL ONE (DC1)  
12 | 00000012 | DEVICE CONTROL TWO (DC2)  
13 | 00000013 | DEVICE CONTROL THREE (DC3)  
14 | 00000014 | DEVICE CONTROL FOUR (DC4)  
15 | 00000015 | NEGATIVE ACKNOWLEDGE (NAK)  
16 | 00000016 | SYNCHRONOUS IDLE (SYN)  
17 | 00000017 | END OF TRANSMISSION BLOCK (ETB)  
18 | 00000018 | CANCEL (CAN)  
19 | 00000019 | END OF MEDIUM (EM)  
1A | 0000001A | SUBSTITUTE (SUB)
```

1B | 0000001B | ESCAPE (ESC)
1C | 0000001C | FILE SEPARATOR (IS4)
1D | 0000001D | GROUP SEPARATOR (IS3)
1E | 0000001E | RECORD SEPARATOR (IS2)
1F | 0000001F | UNIT SEPARATOR (IS1)
20 | 00000020 | SPACE
30 | 00000030 | DIGIT ZERO
31 | 00000031 | DIGIT ONE
32 | 00000032 | DIGIT TWO
33 | 00000033 | DIGIT THREE
34 | 00000034 | DIGIT FOUR
35 | 00000035 | DIGIT FIVE
36 | 00000036 | DIGIT SIX
37 | 00000037 | DIGIT SEVEN
38 | 00000038 | DIGIT EIGHT
39 | 00000039 | DIGIT NINE
3A | 00002446 | OCR BRANCH BANK IDENTIFICATION
3B | 00002447 | OCR AMOUNT OF CHECK
3C | 00002448 | OCR DASH
3D | 00002449 | OCR CUSTOMER ACCOUNT NUMBER
7F | 0000007F | DELETE (DEL)

AUTHOR

Copyright (C) 2002-2016 Guido Flohr <<http://www.guido-flohr.net/>>
(<mailto:guido.flohr@cantanea.com>), all rights reserved. See the source code for
details!code for details!

SEE ALSO

Locale::RecodeData(3), Locale::Recode(3), perl(1)