



Full credit is given to the above companies including the Operating System (OS) that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'runlevel.8'

\$ man runlevel.8

RUNLEVEL(8) runlevel RUNLEVEL(8)

NAME

runlevel - Print previous and current SysV runlevel

SYNOPSIS

runlevel [options...]

OVERVIEW

"Runlevels" are an obsolete way to start and stop groups of services used in SysV init. systemd provides a compatibility layer that maps runlevels to targets, and associated binaries like runlevel. Nevertheless, only one runlevel can be "active" at a given time, while systemd can activate multiple targets concurrently, so the mapping to runlevels is confusing and only approximate. Runlevels should not be used in new code, and are mostly useful as a shorthand way to refer the matching systemd targets in kernel boot parameters.

Table 1. Mapping between runlevels and systemd targets

```

????????????????????????????????????
?Runlevel ? Target      ?
????????????????????????????????????
?0    ? poweroff.target ?
????????????????????????????????????
?1    ? rescue.target   ?

```

????????????????????????????????

?2, 3, 4 ? multi-user.target ?

????????????????????????????????

?5 ? graphical.target ?

????????????????????????????????

?6 ? reboot.target ?

????????????????????????????????

DESCRIPTION

runlevel prints the previous and current SysV runlevel if they are known.

The two runlevel characters are separated by a single space character. If a runlevel cannot be determined, N is printed instead. If neither can be determined, the word "unknown" is printed.

Unless overridden in the environment, this will check the utmp database for recent runlevel changes.

OPTIONS

The following option is understood:

--help

Print a short help text and exit.

EXIT STATUS

If one or both runlevels could be determined, 0 is returned, a non-zero failure code otherwise.

ENVIRONMENT

\$RUNLEVEL

If \$RUNLEVEL is set, runlevel will print this value as current runlevel and ignore utmp.

\$PREVLEVEL

If \$PREVLEVEL is set, runlevel will print this value as previous runlevel and ignore utmp.

FILES

/run/utmp

The utmp database runlevel reads the previous and current runlevel from.

SEE ALSO

systemd(1), systemd.target(5), systemctl(1)

systemd 249

RUNLEVEL(8)