



## ***Rocky Enterprise Linux 9.2 Manual Pages on command 'pam\_securetty.8'***

**C:\>man pam\_securetty.8**

PAM\_SECURETTY(8)                      Linux-PAM Manual                      PAM\_SECURETTY(8)

### NAME

pam\_securetty - Limit root login to special devices

### SYNOPSIS

pam\_securetty.so [debug]

### DESCRIPTION

pam\_securetty is a PAM module that allows root logins only if the user is logging in on a "secure" tty, as defined by the listing in /etc/securetty. pam\_securetty also checks to make sure that /etc/securetty is a plain file and not world writable. It will also allow root logins on the tty specified with console= switch on the kernel command line and on ttys from the /sys/class/tty/console/active. This module has no effect on non-root users and requires that the application fills in the PAM\_TTY item correctly.

For canonical usage, should be listed as a required authentication method before any sufficient authentication methods.

### OPTIONS

debug

Print debug information.

noconsole

Do not automatically allow root logins on the kernel console device, as specified on the kernel command line or by the sys file, if it is not also specified in the /etc/securetty file.

## MODULE TYPES PROVIDED

Only the auth module type is provided.

## RETURN VALUES

### PAM\_SUCCESS

The user is allowed to continue authentication. Either the user is not root, or the root user is trying to log in on an acceptable device.

### PAM\_AUTH\_ERR

Authentication is rejected. Either root is attempting to log in via an unacceptable device, or the `/etc/securetty` file is world writable or not a normal file.

### PAM\_INCOMPLETE

An application error occurred. `pam_securetty` was not able to get information it required from the application that called it.

### PAM\_SERVICE\_ERR

An error occurred while the module was determining the user's name or tty, or the module could not open `/etc/securetty`.

### PAM\_USER\_UNKNOWN

The module could not find the user name in the `/etc/passwd` file to verify whether the user had a UID of 0. Therefore, the results of running this module are ignored.

## EXAMPLES

```
auth required pam_securetty.so
```

```
auth required pam_unix.so
```

## SEE ALSO

`securetty(5)`, `pam.conf(5)`, `pam.d(5)`, `pam(7)`

## AUTHOR

`pam_securetty` was written by Elliot Lee <[sopwith@cuc.edu](mailto:sopwith@cuc.edu)>.