



### ***Windows PowerShell Get-Help on Cmdlet 'Block-SmbClientAccessToServer'***

***PS:\>Get-HELP Block-SmbClientAccessToServer -Full***

#### **NAME**

Block-SmbClientAccessToServer

#### **SYNOPSIS**

#### **SYNTAX**

Block-SmbClientAccessToServer [-Name] <String[]> -IdentifierType {SHA256 | ISSUER} -Identifier <String> [-Description <String>] [-Force] [-CimSession <CimSession[]>]

[-ThrottleLimit <Int32>] [-AsJob] [-WhatIf] [-Confirm] [<CommonParameters>]

Block-SmbClientAccessToServer -InputObject <CimInstance[]> -IdentifierType {SHA256 | ISSUER} -Identifier <String> [-Description <String>] [-Force] [-CimSession <CimSession[]>] [-ThrottleLimit <Int32>] [-AsJob] [-WhatIf] [-Confirm] [<CommonParameters>]

#### **DESCRIPTION**

#### **PARAMETERS**

-Name <String[]>

Required? true

Position? 2

Default value

Accept pipeline input? true (ByPropertyName)

Accept wildcard characters? false

-InputObject <CimInstance[]>

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-IdentifierType

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Identifier <String>

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Description <String>

Required? false  
Position? named  
Default value  
Accept pipeline input? false  
Accept wildcard characters? false

-Force [<SwitchParameter>]

Required? false  
Position? named  
Default value False  
Accept pipeline input? false  
Accept wildcard characters? false

-CimSession <CimSession[]>

Required? false  
Position? named  
Default value  
Accept pipeline input? false  
Accept wildcard characters? false

-ThrottleLimit <Int32>

Required? false  
Position? named  
Default value 0  
Accept pipeline input? false  
Accept wildcard characters? false

-AsJob [<SwitchParameter>]

Required? false  
Position? named  
Default value False  
Accept pipeline input? false  
Accept wildcard characters? false

#### -WhatIf [<SwitchParameter>]

Required? false  
Position? named  
Default value  
Accept pipeline input? false  
Accept wildcard characters? false

#### -Confirm [<SwitchParameter>]

Required? false  
Position? named  
Default value  
Accept pipeline input? false  
Accept wildcard characters? false

#### <CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

## INPUTS

## OUTPUTS

Microsoft.Management.Infrastructure.CimInstance[]

RELATED LINKS