



python



PowerShell

FPDF Library
PDF generator

Full credit is given to the above companies including the OS that this PDF file was generated!

PowerShell Get-Help on command 'Clear-UevConfiguration'

PS C:\Users\wahid> Get-Help Clear-UevConfiguration

NAME

Clear-UevConfiguration

SYNOPSIS

Clears UE-V configuration settings.

SYNTAX

Clear-UevConfiguration [-Computer] [-Confirm] [-ContactITDescription]
[-ContactITUrl] [-DontSyncWindows8AppSettings] [-FirstUseNotificationEnabled]
[-MaxPackageSizeInBytes] [-SettingsImportNotifyDelayInSeconds]
[-SettingsImportNotifyEnabled] [-SettingsStoragePath]
[-SettingsTemplateCatalogPath] [-SyncEnabled] [-SyncMethod]
[-SyncOverMeteredNetwork] [-SyncOverMeteredNetworkWhenRoaming]
[-SyncProviderPingEnabled] [-SyncTimeoutInMilliseconds]
[-SyncUnlistedWindows8Apps] [-TrayIconEnabled] [-VdiCollectionName]
[-WaitForSyncOnApplicationStart] [-WaitForSyncOnLogon]
[-WaitForSyncTimeoutInMilliseconds] [-WhatIf] [<CommonParameters>]

Clear-UevConfiguration [-Confirm] [-CurrentComputerUser]
[-DontSyncWindows8AppSettings] [-MaxPackageSizeInBytes]

[-SettingsImportNotifyDelayInSeconds] [-SettingsImportNotifyEnabled]
[-SettingsStoragePath] [-SyncEnabled] [-SyncMethod] [-SyncOverMeteredNetwork]
[-SyncOverMeteredNetworkWhenRoaming] [-SyncProviderPingEnabled]
[-SyncTimeoutInMilliseconds] [-SyncUnlistedWindows8Apps] [-VdiCollectionName]
[-WaitForSyncOnApplicationStart] [-WaitForSyncOnLogon]
[-WaitForSyncTimeoutInMilliseconds] [-WhatIf] [<CommonParameters>]

DESCRIPTION

The Clear-UevConfiguration cmdlet clears Microsoft User Experience Virtualization (UE-V) configuration settings. If you specify the CurrentComputerUser parameter, the cmdlet clears the settings that you specify for the current user only. If you specify the Computer parameter, the cmdlet clears the settings that you specify for all users on the computer. You must have administrative credentials to use this cmdlet to clear settings for all users on the computer. If you do not specify the CurrentComputerUser or Computer parameter, the cmdlet clears the settings that you specify for the current user only.

PARAMETERS

-Computer [<SwitchParameter>]

Indicates that the cmdlet clears the settings for all users on the computer.

-Confirm [<SwitchParameter>]

Prompts you for confirmation before running the cmdlet.

-ContactITDescription [<SwitchParameter>]

Indicates that the cmdlet clears the setting for the description of the Contact IT link.

-ContactITUrl [<SwitchParameter>]

Indicates that the cmdlet clears the setting for the URL of the Contact IT link.

-CurrentComputerUser [<SwitchParameter>]

Indicates that the cmdlet clears the settings that you specify for the current user only.

-DontSyncWindows8AppSettings [<SwitchParameter>]

Indicates that the cmdlet clears the setting for not synchronizing settings for Windows 8 apps.

-FirstUseNotificationEnabled [<SwitchParameter>]

Indicates that the cmdlet clears the setting for the notification of first-use.

-MaxPackageSizeInBytes [<SwitchParameter>]

Indicates that the cmdlet clears the setting for the maximum package size.

-SettingsImportNotifyDelayInSeconds [<SwitchParameter>]

Indicates that the cmdlet clears the setting for the delay before UE-V notifies the user about the settings import.

-SettingsImportNotifyEnabled [<SwitchParameter>]

Indicates that the cmdlet clears the setting for the notification of settings import.

-SettingsStoragePath [<SwitchParameter>]

Indicates that the cmdlet clears the setting for the path of the location where UE-V stores the user settings.

-SettingsTemplateCatalogPath [<SwitchParameter>]

Indicates that the cmdlet clears the setting for the path of the location where UE-V stores the settings template catalog.

-SyncEnabled [<SwitchParameter>]

Indicates that the cmdlet clears the setting that enables the synchronization of settings.

-SyncMethod [<SwitchParameter>]

Indicates that the cmdlet clears the setting for the method of the synchronization of settings.

-SyncOverMeteredNetwork [<SwitchParameter>]

Indicates that the cmdlet clears the setting for synchronization over metered connections.

-SyncOverMeteredNetworkWhenRoaming [<SwitchParameter>]

Indicates that the cmdlet clears the setting for synchronization over a metered connection that is roaming.

-SyncProviderPingEnabled [<SwitchParameter>]

Indicates that the cmdlet clears the setting that enables the sync provider to ping for network access before doing a sync.

-SyncTimeoutInMilliseconds [<SwitchParameter>]

Indicates that the cmdlet clears the setting for the timeout before UE-V synchronizes settings from the settings repository.

-SyncUnlistedWindows8Apps [<SwitchParameter>]

Indicates that the cmdlet clears the setting for the synchronization of unlisted Windows 8 apps.

-TrayIconEnabled [<SwitchParameter>]

Indicates that the cmdlet clears the setting for the icon in the notification area.

-VdiCollectionName [<SwitchParameter>]

Indicates that the cmdlet performs synchronization in a pooled VDI-type environment when computers are not persistent.

-WaitForSyncOnApplicationStart [<SwitchParameter>]

Indicates that the cmdlet clears the setting for waiting for synchronization to finish before the user can start an application.

-WaitForSyncOnLogon [<SwitchParameter>]

Indicates that the cmdlet clears the setting for waiting for synchronization to finish before the user can log on.

-WaitForSyncTimeoutInMilliseconds [<SwitchParameter>]

For internal use only.

-WhatIf [<SwitchParameter>]

Shows what would happen if the cmdlet runs. The cmdlet is not run.

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

Example 1: Clear the setting for maximum package size for all users

```
PS C:\> Clear-UevConfiguration -Computer -MaxPackageSizeInBytes
```

This command clears the setting for maximum package size for all users on the computer.

Example 2: Clear the setting for maximum package size for the current user

```
PS C:\> Clear-UevConfiguration -CurrentComputerUser -MaxPackageSizeInBytes
```

This command clears the setting for maximum package size for the current user.

Example 3: Clear the setting for maximum package size by default for the current user

```
PS C:\> Clear-UevConfiguration -MaxPackageSizeInBytes
```

This command clears the setting for maximum package size by default for the current user.

--- Example 4: Clear multiple settings for the current user ---

```
PS C:\> Clear-UevConfiguration -MaxPackageSizeInBytes  
-SyncTimeoutInMilliseconds
```

This command clears the settings for maximum package size and synchronization timeout for the current user.

REMARKS

To see the examples, type: "get-help Clear-UevConfiguration -examples".

For more information, type: "get-help Clear-UevConfiguration -detailed".

For technical information, type: "get-help Clear-UevConfiguration -full".

For online help, type: "get-help Clear-UevConfiguration -online"