



Windows PowerShell Get-Help on Cmdlet 'Disable-AzBatchAutoScale'

PS:\>Get-HELP Disable-AzBatchAutoScale -Full

NAME

Disable-AzBatchAutoScale

SYNOPSIS

Disables automatic scaling of a pool.

SYNTAX

```
Disable-AzBatchAutoScale [-Id] <System.String> -BatchContext
<Microsoft.Azure.Commands.Batch.BatchAccountContext> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[<CommonParameters>]
```

DESCRIPTION

The Disable-AzBatchAutoScale cmdlet disables automatic scaling of the specified pool.

PARAMETERS

-BatchContext <Microsoft.Azure.Commands.Batch.BatchAccountContext>

Specifies the BatchAccountContext instance that this cmdlet uses to interact with the Batch service. If you use the Get-AzBatchAccount cmdlet to get your

BatchAccountContext, then Microsoft Entra authentication will be used when interacting with the Batch service. To use shared key authentication instead, use the

Get-AzBatchAccountKey cmdlet to get a BatchAccountContext object with its access keys populated. When using shared key authentication, the primary access key is

used by default. To change the key to use, set the BatchAccountContext.KeyInUse property.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByValue)
Accept wildcard characters?	false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Id <System.String>

Specifies the object ID of the pool.

Required?	true
Position?	0
Default value	None
Accept pipeline input?	True (ByPropertyName, ByValue)
Accept wildcard characters?	false

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.String

Microsoft.Azure.Commands.Batch.BatchAccountContext

OUTPUTS

System.Void

NOTES

----- Example 1: Disable automatic scaling of a pool -----

Disable-AzBatchAutoScale -Id "MyPool" -BatchContext \$Context

This command disables automatic scaling for the pool named MyPool.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.batch/disable-azbatchautoscale>

Enable-AzBatchAutoScale

Test-AzBatchAutoScale

Azure Batch Cmdlets