



Windows PowerShell Get-Help on Cmdlet 'Disable-AzBatchJob'

PS:\>Get-HELP Disable-AzBatchJob -Full

NAME

Disable-AzBatchJob

SYNOPSIS

Disables a Batch job.

SYNTAX

```
Disable-AzBatchJob [-Id] <System.String> [-DisableJobOption] {Requeue | Terminate | Wait} -BatchContext  
<Microsoft.Azure.Commands.Batch.BatchAccountContext>  
  
[-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]  
[<CommonParameters>]
```

DESCRIPTION

The Disable-AzBatchJob cmdlet disables an Azure Batch job. After you enable a job, new tasks can run. Disabled jobs do not run new tasks. You can enable a disabled job later.

PARAMETERS

-BatchContext <Microsoft.Azure.Commands.Batch.BatchAccountContext>

Specifies the BatchAccountContext instance that this cmdlet uses to interact with the Batch service. If you use the Get-AzBatchAccount cmdlet to get your

BatchAccountContext, then Microsoft Entra authentication will be used when interacting with the Batch service. To use shared key authentication instead, use the

Get-AzBatchAccountKey cmdlet to get a BatchAccountContext object with its access keys populated. When using shared key authentication, the primary access key is

used by default. To change the key to use, set the BatchAccountContext.KeyInUse property.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByValue)
Accept wildcard characters?	false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-DisableJobOption <Microsoft.Azure.Batch.Common.DisableJobOption>

Specifies what to do with active tasks associated with the job that this cmdlet disables. Valid values are: - Requeue

- Terminate

- Wait

Required?	true
-----------	------

Position? 1
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Id <System.String>

Specifies the ID of the job that this cmdlet disables.

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName, ByValue)
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.String

Microsoft.Azure.Commands.Batch.BatchAccountContext

OUTPUTS

System.Void

NOTES

----- Example 1: Disable a Batch job -----

```
Disable-AzBatchJob -Id "Job-000001" -DisableJobOption "Terminate" -BatchContext $Context
```

This command disables the job that has the ID Job-000001. The command terminates active tasks for the job. Use the `Get-AzBatchAccountKey` cmdlet to assign a context to the `$Context` variable.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.batch/disable-azbatchjob>

[Enable-AzBatchJob](#)

[Get-AzBatchAccountKey](#)

[Get-AzBatchJob](#)

[New-AzBatchJob](#)

[Remove-AzBatchJob](#)

[Stop-AzBatchJob](#)

[Azure Batch Cmdlets](#)