



Windows PowerShell Get-Help on Cmdlet 'Enable-AzBatchJob'

PS:\>Get-HELP Enable-AzBatchJob -Full

NAME

Enable-AzBatchJob

SYNOPSIS

Enables a Batch job.

SYNTAX

```
Enable-AzBatchJob [-Id] <System.String> -BatchContext <Microsoft.Azure.Commands.Batch.BatchAccountContext>
[-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[<CommonParameters>]
```

DESCRIPTION

The Enable-AzBatchJob cmdlet enables an Azure Batch job. After you enable a job, new tasks can run.

PARAMETERS

-BatchContext <Microsoft.Azure.Commands.Batch.BatchAccountContext>

Specifies the BatchAccountContext instance that this cmdlet uses to interact with the Batch service. If you use the Get-AzBatchAccount cmdlet to get your

BatchAccountContext, then Microsoft Entra authentication will be used when interacting with the Batch service. To use shared key authentication instead, use the

Get-AzBatchAccountKey cmdlet to get a BatchAccountContext object with its access keys populated. When using shared key authentication, the primary access key is

used by default. To change the key to use, set the BatchAccountContext.KeyInUse property.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByValue)
Accept wildcard characters?	false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Id <System.String>

Specifies the ID of the job that this cmdlet enables.

Required?	true
Position?	0
Default value	None
Accept pipeline input?	True (ByPropertyName, ByValue)
Accept wildcard characters?	false

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters](https://go.microsoft.com/fwlink/?LinkID=113216) (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.Batch.BatchAccountContext

OUTPUTS

System.Void

NOTES

----- Example 1: Enable a Batch job -----

```
Enable-AzBatchJob -Id "Job-000001" -BatchContext $Context
```

This command enables the job that has the ID Job-000001. Use the Get-AzBatchAccountKey cmdlet to assign a context to the \$Context variable.

Online Version: <https://learn.microsoft.com/powershell/module/az.batch/enable-azbatchjob>

Disable-AzBatchJob

Get-AzBatchJob

New-AzBatchJob

Remove-AzBatchJob

Stop-AzBatchJob

Azure Batch Cmdlets