



## ***Windows PowerShell Get-Help on Cmdlet 'Enable-AzDataCollection'***

***PS:\>Get-HELP Enable-AzDataCollection -Full***

### NAME

Enable-AzDataCollection

### SYNOPSIS

Enables Azure PowerShell to collect data to improve the user experience with the Azure PowerShell cmdlets. Executing this cmdlet opts in to data collection for the current user on the current machine. Data is collected by default unless you explicitly opt out.

### SYNTAX

```
Enable-AzDataCollection [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]  
[<CommonParameters>]
```

### DESCRIPTION

The 'Enable-AzDataCollection' cmdlet is used to opt in to data collection. Azure PowerShell automatically collects telemetry data by default. Microsoft aggregates

collected data to identify patterns of usage, to identify common issues, and to improve the experience of Azure PowerShell. Microsoft Azure PowerShell doesn't collect

any private or personal data. To disable data collection, you must explicitly opt out by executing ``Disable-AzDataCollection``.

## PARAMETERS

`-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>`

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

`-Confirm <System.Management.Automation.SwitchParameter>`

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

`-WhatIf <System.Management.Automation.SwitchParameter>`

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about\\_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

## INPUTS

None

## OUTPUTS

System.Void

## NOTES

--- Example 1: Enabling data collection for the current user ---

Enable-AzDataCollection

## RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.accounts/enable-azdatacollection>

Disable-AzDataCollection

