



Windows PowerShell Get-Help on Cmdlet 'Enable-AzStorageStaticWebsite'

PS:\>Get-HELP Enable-AzStorageStaticWebsite -Full

NAME

Enable-AzStorageStaticWebsite

SYNOPSIS

Enable static website for the Azure Storage account.

SYNTAX

```
Enable-AzStorageStaticWebsite [[-IndexDocument] <System.String>] [[-ErrorDocument404Path] <System.String>]
[-Context
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext>] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Enable-AzStorageStaticWebsite cmdlet enables static website for the Azure Storage account.

-Context <Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext>

Azure Storage Context Object

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName, ByValue)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ErrorDocument404Path <System.String>

The path to the error document that should be shown when a 404 is issued (meaning, when a browser requests a page that does not exist.)

Required? false

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-IndexDocument <System.String>

The name of the index document in each directory.

Required? false

Position? 0

Default value None
Accept pipeline input? False
Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Display Static Website setting in ServiceProperties.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext

OUTPUTS

Microsoft.WindowsAzure.Commands.Storage.Model.ResourceModel.PSStaticWebsiteProperties

NOTES

Example 1: Enable static website for the Azure Storage account

```
Enable-AzStorageStaticWebsite -IndexDocument $indexdoc -ErrorDocument404Path $errordoc
```

This command enables static website for the Azure Storage account.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.storage/enable-azstoragestaticwebsite>