



Windows PowerShell Get-Help on Cmdlet 'Enable-AzureRmAlias'

PS:\>Get-HELP Enable-AzureRmAlias -Full

NAME

Enable-AzureRmAlias

SYNOPSIS

Enables AzureRm prefix aliases for Az modules.

SYNTAX

```
Enable-AzureRmAlias [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Module  
<System.String[]>]  
[-PassThru] [-Scope {Local | Process | CurrentUser | LocalMachine}] [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

Enables AzureRm prefix aliases for Az modules. If -Module is specified, only modules listed will have aliases enabled. Otherwise all AzureRm aliases are enabled.

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Module <System.String[]>

Indicates which modules to enable aliases for. If none are specified, default is all modules.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

If specified, cmdlet will return all aliases enabled

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-Scope <System.String>

Indicates what scope aliases should be enabled for. Default is 'Local'

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

System.String

NOTES

----- Example 1 -----

Enable-AzureRmAlias

Enables all AzureRm prefixes for the current PowerShell session.

----- Example 2 -----

Enable-AzureRmAlias -Module Az.Accounts -Scope CurrentUser

Enables AzureRm aliases for the Az.Accounts module for both the current process and for the current user.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.accounts/enable-azurermaliases>