



Windows PowerShell Get-Help on Cmdlet 'Enable-BcdElementBootDebug'

PS:\>Get-HELP Enable-BcdElementBootDebug -Full

NAME

Enable-BcdElementBootDebug

SYNTAX

Enable-BcdElementBootDebug [-Id] <string> [[-Store] <BcdStoreInfo>] [-Force] [-WhatIf] [-Confirm]

[<CommonParameters>]

Enable-BcdElementBootDebug [-Entry] <BcdEntryInfo> [-Force] [-WhatIf] [-Confirm] [<CommonParameters>]

PARAMETERS

-Confirm

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	cf
Dynamic?	false

-Entry <BcdEntryInfo>

Required?	true
Position?	0
Accept pipeline input?	true (ByValue)
Parameter set name	Entry
Aliases	None
Dynamic?	false

-Force

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	None
Dynamic?	false

-Id <string>

Required?	true
Position?	0
Accept pipeline input?	true (ByValue, ByPropertyName)
Parameter set name	Id
Aliases	Identifier
Dynamic?	false

-Store <BcdStoreInfo>

Required?	false
Position?	1
Accept pipeline input?	false
Parameter set name	Id

Aliases	None
Dynamic?	false

-WhatIf

Required?	false
Position?	Named
Accept pipeline input?	false
Parameter set name	(All)
Aliases	wi
Dynamic?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String
Microsoft.Windows.Bcd.Cmdlets.BcdExtensions.BcdEntryInfo

OUTPUTS

System.Object

ALIASES

None

REMARKS

None

