



Windows PowerShell Get-Help on Cmdlet 'Export-BCCachePackage'

PS:\>Get-HELP Export-BCCachePackage -Full

NAME

Export-BCCachePackage

SYNOPSIS

Exports a cache package.

SYNTAX

Export-BCCachePackage [-AsJob] [-CimSession <CimSession[]>] [-Confirm] -Destination <String> -ExportDataCache
[-Force] [-ThrottleLimit <Int32>] [-WhatIf]
[<CommonParameters>]

Export-BCCachePackage [[-StagingPath] <String>] [-AsJob] [-CimSession <CimSession[]>] [-Confirm] -Destination
<String> [-Force] [-OutputReferenceFile <String>]
[-ThrottleLimit <Int32>] [-WhatIf] [<CommonParameters>]

DESCRIPTION

The Export-BCCachePackage cmdlet exports a cache package.

PARAMETERS

-AsJob [<SwitchParameter>]

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete.

The cmdlet immediately returns an object that represents the job and then displays the command prompt. You can continue to work in the session while the job

completes. To manage the job, use the ``*-Job`` cmdlets. To get the job results, use the `Receive-Job` (<https://go.microsoft.com/fwlink/?LinkID=113372>) cmdlet.

For more information about Windows PowerShell background jobs, see `about_Jobs` (<https://go.microsoft.com/fwlink/?LinkID=113251>).

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-CimSession <CimSession[]>

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a `New-CimSession`

(<https://go.microsoft.com/fwlink/p/?LinkId=227967>) or `[Get-CimSession]`(<https://go.microsoft.com/fwlink/p/?LinkId=227966>) cmdlet. The default is the current session on the local computer.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Confirm [<SwitchParameter>]

Prompts you for confirmation before running the cmdlet.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-Destination <String>

Specifies the folder location where the data package is stored.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-ExportDataCache [<SwitchParameter>]

Specifies that the contents of the local data cache are included in the package.

Required?	true
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-Force [<SwitchParameter>]

Forces the command to run without asking for user confirmation.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False

Accept wildcard characters? false

-OutputReferenceFile <String>

Specifies the folder location where the output reference file is generated.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-StagingPath <String>

Specifies the folder location of the cache files that this cmdlet packages. These files are generated from the Publish-BCFileContent cmdlet.

Required? false

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ThrottleLimit <Int32>

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of `0` is entered, then

Windows PowerShell calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are running on the computer. The throttle limit

applies only to the current cmdlet, not to the session or to the computer.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

None

NOTES

----- Example 1: Export content -----

```
PS C:\> Export-BCDataPackage -Destination "D:\temp"
```

This command exports all content that has been hashed by using the Publish-BCFileContent and Publish-BCWebContent cmdlets. The command exports the package that contains this data to D:\temp.

RELATED LINKS

Online

Version:

https://learn.microsoft.com/powershell/module/branchcache/export-bccachepackage?view=windowsserver2022-ps&wt.mc_id=ps-gethelp

Import-BCCachePackage

Publish-BCFileContent

Publish-BCWebContent