



## ***Windows PowerShell Get-Help on Cmdlet 'Get-AzApplicationGatewayAutoscaleConfiguration'***

***PS:\>Get-HELP Get-AzApplicationGatewayAutoscaleConfiguration -Full***

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

### NAME

Get-AzApplicationGatewayAutoscaleConfiguration

### SYNOPSIS

Gets the Autoscale Configuration of the Application Gateway.

### SYNTAX

Get-AzApplicationGatewayAutoscaleConfiguration -ApplicationGateway

<Microsoft.Azure.Commands.Network.Models.PSApplicationGateway> [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]

[<CommonParameters>]

### DESCRIPTION

The Get-AzApplicationGatewayAutoscaleConfiguration cmdlet gets Autoscale Configuration of the Application Gateway.

## PARAMETERS

-ApplicationGateway <Microsoft.Azure.Commands.Network.Models.PSApplicationGateway>

The applicationGateway

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see

about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

## INPUTS

Microsoft.Azure.Commands.Network.Models.PSApplicationGateway

## OUTPUTS

## NOTES

----- Example 1 -----

```
$gw = Get-AzApplicationGateway -Name $appgwName -ResourceGroupName $resgpName  
$autoscaleConfiguration = Get-AzApplicationGatewayAutoscaleConfiguration -ApplicationGateway $gw  
$autoscaleConfiguration.MinCapacity
```

The first command gets the application gateway and stores it in \$gw variable. The second command extracts out the autoscale configuration from the application gateway.

## RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.network/get-azapplicationgatewayautoscaleconfiguration>

New-AzApplicationGatewayAutoscaleConfiguration

Remove-AzApplicationGatewayAutoscaleConfiguration

Set-AzApplicationGatewayAutoscaleConfiguration