



Windows PowerShell Get-Help on Cmdlet 'Get-AzAttestationDefaultProvider'

PS:\>Get-HELP Get-AzAttestationDefaultProvider -Full

NAME

Get-AzAttestationDefaultProvider

SYNOPSIS

Get the default provider by location.

SYNTAX

```
Get-AzAttestationDefaultProvider [-SubscriptionId <String[]>] [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend
<SendAsyncStep[]>] [-HttpPipelinePrepend
<SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials]
[<CommonParameters>]
```

```
Get-AzAttestationDefaultProvider -Location <String> [-SubscriptionId <String[]>] [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>]
[-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]
```

```
Get-AzAttestationDefaultProvider -InputObject <IAttestationIdentity> [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>]
```

[-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]

DESCRIPTION

Get the default provider by location.

PARAMETERS

-Location <String>

The location of the default provider.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String[]>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <IAttestationIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.Attestation.Models.IAttestationIdentity

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Attestation.Models.Api20201001.IAttestationProvider

Microsoft.Azure.PowerShell.Cmdlets.Attestation.Models.Api20201001.IAttestationProviderListResult

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help

about_Hash_Tables.

INPUTOBJECT <IAttestationIdentity>: Identity Parameter

[Id <String>]: Resource identity path

[Location <String>]: The location of the default provider.

[PrivateEndpointConnectionName <String>]: The name of the private endpoint connection associated with the Azure resource

[ProviderName <String>]: Name of the attestation provider.

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[SubscriptionId <String>]: The ID of the target subscription.

----- EXAMPLE 1 -----

```
PS C:\>Get-AzAttestationDefaultProvider -Location "East US"
```

----- EXAMPLE 2 -----

```
PS C:\>Get-AzAttestationDefaultProvider
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.attestation/get-azattestationdefaultprovider>