



Windows PowerShell Get-Help on Cmdlet 'Get-AzIotHubDeviceParent'

PS:\>Get-HELP Get-AzIotHubDeviceParent -Full

NAME

Get-AzIotHubDeviceParent

SYNOPSIS

Get the parent device of the specified device.

SYNTAX

```
Get-AzIotHubDeviceParent [-InputObject] <Microsoft.Azure.Commands.Management.IotHub.Models.PSIotHub>
[-DeviceId] <System.String> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[<CommonParameters>]
```

```
Get-AzIotHubDeviceParent [-ResourceGroupName] <System.String> [-DeviceId] <System.String> [-IotHubName]
<System.String> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[<CommonParameters>]
```

```
Get-AzIotHubDeviceParent [-ResourceId] <System.String> [-DeviceId] <System.String> [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>]
[<CommonParameters>]
```

[<CommonParameters>]

DESCRIPTION

Get the parent device of the specified non-edge device.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DeviceId <System.String>

Id of non-edge device.

Required? true

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Management.IotHub.Models.PSIotHub>

IotHub object

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-lotHubName <System.String>

Name of the lot Hub

Required? true

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Name of the Resource Group

Required? true

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceId <System.String>

lotHub Resource Id

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see

about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Management.IotHub.Models.PSlotHub

System.String

OUTPUTS

Microsoft.Azure.Commands.Management.IotHub.Models.PSDevice

NOTES

----- Example 1 -----

Get-AzIotHubDeviceParent -ResourceGroupName "myresourcegroup" -IotHubName "myiothub" -DeviceId "myDevice1"

DeviceId : myParentDevice1
GenerationId : 637148941292917073
ETag : "NzlyMDI4MTk3"
LastActivityTime : 1/1/0001 12:00:00 AM
ConnectionState : Disconnected
ConnectionStateUpdatedTime : 1/1/0001 12:00:00 AM
Status : Enabled
StatusReason :
StatusUpdatedTime : 1/17/2020 10:15:04 PM

CloudToDeviceMessageCount : 0

Authentication : Sas

EdgeEnabled : True

DeviceScope : ms-azure-iot-edge://myParentDevice1-637176526047419634

Get the parent device of the specified non-edge device.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.iothub/get-aziothubdeviceparent>