



Windows PowerShell Get-Help on Cmdlet 'Get-AzLoadBalancerBackendAddressPool'

PS:\>Get-HELP Get-AzLoadBalancerBackendAddressPool -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Get-AzLoadBalancerBackendAddressPool

SYNOPSIS

Get-AzLoadBalancerBackendAddressPool retrieves one or more backend address pools associated with a load balancer.

SYNTAX

Get-AzLoadBalancerBackendAddressPool [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -LoadBalancer

<Microsoft.Azure.Commands.Network.Models.PSLoadBalancer> [-Name <System.String>] [<CommonParameters>]

Get-AzLoadBalancerBackendAddressPool [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -LoadBalancerName

<System.String> [-Name <System.String>] -ResourceGroupName <System.String> [<CommonParameters>]

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -ResourceId

<System.String> [<CommonParameters>]

DESCRIPTION

Get-AzLoadBalancerBackendAddressPool retrieves one or more backend address pools associated with a load balancer.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-LoadBalancer <Microsoft.Azure.Commands.Network.Models.PSLoadBalancer>

{{ Fill LoadBalancer Description }}

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-LoadBalancerName <System.String>

The name of the load balancer.

Required? true

Position? named

Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Name <System.String>

The name of the backend address pool.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource group name of the load balancer.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-ResourceId <System.String>

Required? true
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,
OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Network.Models.PSLoadBalancer

System.String

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSBackendAddressPool

NOTES

----- Example 1 -----

Get single backend under loadbalancer

\$lb = Get-AzLoadBalancer -ResourceGroupName \$resourceGroup -Name \$loadBalancerName

Get all backends under loadbalancer

\$lb | Get-AzLoadBalancerBackendAddressPool

----- Example 2 -----

#Get specific backend from loadbalancer

\$lb | Get-AzLoadBalancerBackendAddressPool -Name \$backendPool1

----- Example 3 -----

#Get a backend by resource Id

Get-AzLoadBalancerBackendAddressPool -ResourceId \$backendPool1.Id

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/get-azloadbalancerbackendaddresspool>