



Windows PowerShell Get-Help on Cmdlet 'Get-AzSecurityAutoProvisioningSetting'

PS:\>Get-HELP Get-AzSecurityAutoProvisioningSetting -Full

NAME

Get-AzSecurityAutoProvisioningSetting

SYNOPSIS

Gets the security automatic provisioning settings

SYNTAX

```
Get-AzSecurityAutoProvisioningSetting [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name  
<System.String> [<CommonParameters>]
```

```
Get-AzSecurityAutoProvisioningSetting [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -ResourceId  
<System.String> [<CommonParameters>]
```

DESCRIPTION

Automatic Provisioning Settings let you decide whether you want Azure Security Center to automatically provision a security agent that will be installed on your VMs.

The security agent will monitor your VM to create security alerts and monitor the security compliance of the VM.

PARAMETERS

`-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>`

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

`-Name <System.String>`

Resource name.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

`-ResourceId <System.String>`

Resource ID.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

`<CommonParameters>`

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,
OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

OUTPUTS

Microsoft.Azure.Commands.Security.Models.AutoProvisioningSettings.PSSecurityAutoProvisioningSetting

NOTES

----- Example 1 -----

Get-AzSecurityAutoProvisioningSetting -Name "default"

Id	Name	AutoProvision
----	------	---------------

--	---	-----
----	-----	-------

/subscriptions/487bb485-b5b0-471e-9c0d-10717612f869/providers/Microsoft.Security/autoProvisioningSettings/default

default On

Gets the auto provisioning setting for the subscription

