



Windows PowerShell Get-Help on Cmdlet 'Get-AzSqlServerDisasterRecoveryConfigurationActivity'

PS:\>Get-HELP Get-AzSqlServerDisasterRecoveryConfigurationActivity -Full

NAME

Get-AzSqlServerDisasterRecoveryConfigurationActivity

SYNOPSIS

Gets activity for a database server system recovery configuration.

SYNTAX

```
Get-AzSqlServerDisasterRecoveryConfigurationActivity [-ResourceGroupName] <System.String> [-ServerName]
<System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-OperationId]
<System.Nullable`1[System.Guid]>]
-ServerDisasterRecoveryConfigurationName <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Get-AzSqlServerDisasterRecoveryConfigurationActivity cmdlet gets activity for a SQL database server system recovery configuration.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-OperationId <System.Nullable`1[System.Guid]>

Specifies the operation ID.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of the resource group.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ServerDisasterRecoveryConfigurationName <System.String>

Specifies the name of the server system recovery configuration.

Required? true

Position? named

Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-ServerName <System.String>

Specifies the name of the server.

Required? true
Position? 1
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,
OutBuffer, PipelineVariable, and OutVariable. For more information, see
about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

System.Nullable`1[[System.Guid, System.Private.CoreLib, Version=4.0.0.0, Culture=neutral, PublicKeyToken=7cec85d7bea7798e]]

OUTPUTS

Microsoft.Azure.Commands.Sql.ServerDisasterRecoveryConfiguration.Model.AzureSqlServerDisasterRecoveryConfigurationActivityModel

NOTES

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.sql/get-azsqlserverdisasterrecoveryconfigurationactivity>
SQL Database Documentation <https://learn.microsoft.com/azure/sql-database/>