



Windows PowerShell Get-Help on Cmdlet 'Get-AzStorageMoverJobDefinition'

PS: \>Get-HELP Get-AzStorageMoverJobDefinition -Full

NAME

Get-AzStorageMoverJobDefinition

SYNOPSIS

Gets a Job Definition resource.

SYNTAX

```
Get-AzStorageMoverJobDefinition -ProjectName <String> -ResourceGroupName <String> -StorageMoverName <String>
[-SubscriptionId <String[]>] [-DefaultProfile <PSObject>]
    [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>]
[-ProxyCredential <PSCredential>]
    [-ProxyUseDefaultCredentials] [<CommonParameters>]

Get-AzStorageMoverJobDefinition -Name <String> -ProjectName <String> -ResourceGroupName <String>
-StorageMoverName <String> [-SubscriptionId <String[]>]
    [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend
<SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential
<PSCredential>] [-ProxyUseDefaultCredentials] [<CommonParameters>]
```

```

Get-AzStorageMoverJobDefinition -InputObject <IStorageMoverIdentity> [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>]
[-HttpPipelinePrepend <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]
[-ProxyUseDefaultCredentials] [<CommonParameters>]

```

DESCRIPTION

Gets a Job Definition resource.

PARAMETERS

-Name <String>

The name of the Job Definition resource.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProjectName <String>

The name of the Project resource.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-StorageMoverName <String>

The name of the Storage Mover resource.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-SubscriptionId <String[]>

The ID of the target subscription.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-InputObject <IStorageMoverIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true
Position? named
Default value
Accept pipeline input? true (ByValue)
Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters](https://go.microsoft.com/fwlink/?LinkID=113216) (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.StorageMover.Models.IStorageMoverIdentity

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.StorageMover.Models.Api20231001.IJobDefinition

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help [about_Hash_Tables](#).

INPUTOBJECT <IStorageMoverIdentity>: Identity Parameter

[AgentName <String>]: The name of the Agent resource.

[EndpointName <String>]: The name of the Endpoint resource.

[Id <String>]: Resource identity path

[JobDefinitionName <String>]: The name of the Job Definition resource.

[JobRunName <String>]: The name of the Job Run resource.

[ProjectName <String>]: The name of the Project resource.

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[StorageMoverName <String>]: The name of the Storage Mover resource.

[SubscriptionId <String>]: The ID of the target subscription.

----- EXAMPLE 1 -----

```
PS C:\>Get-AzStorageMoverJobDefinition -ProjectName myProject -ResourceGroupName myResourceGroup  
-StorageMoverName myStorageMover
```

----- EXAMPLE 2 -----

```
PS C:\>Get-AzStorageMoverJobDefinition -ProjectName myProject -ResourceGroupName myResourceGroup  
-StorageMoverName myStorageMover -Name myJob1
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.storage/mover/get-azstoragemoverjobdefinition>