



Windows PowerShell Get-Help on Cmdlet 'Get-AzStorageMoverJobRun'

PS:\>Get-HELP Get-AzStorageMoverJobRun -Full

NAME

Get-AzStorageMoverJobRun

SYNOPSIS

Gets a Job Run resource.

SYNTAX

```
Get-AzStorageMoverJobRun -JobDefinitionName <String> -ProjectName <String> -ResourceGroupName <String>
-StorageMoverName <String> [-SubscriptionId <String[]>]
    [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend
<SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential
    <PSCredential>] [-ProxyUseDefaultCredentials] [<CommonParameters>]

Get-AzStorageMoverJobRun -JobDefinitionName <String> -Name <String> -ProjectName <String>
-ResourceGroupName <String> -StorageMoverName <String> [-SubscriptionId
    <String[]>] [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend
<SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential
    <PSCredential>] [-ProxyUseDefaultCredentials] [<CommonParameters>]
```

```

Get-AzStorageMoverJobRun -InputObject <IStorageMoverIdentity> [-DefaultProfile <PSObject>] [-Break]
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend
    <SendAsyncStep[]>] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials]
[<CommonParameters>]

```

DESCRIPTION

Gets a Job Run resource.

PARAMETERS

-JobDefinitionName <String>

The name of the Job Definition resource.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Name <String>

The name of the Job Run resource.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProjectName <String>

The name of the Project resource.

Required? true

Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.
The name is case insensitive.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-StorageMoverName <String>

The name of the Storage Mover resource.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-SubscriptionId <String[]>

The ID of the target subscription.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

`-InputObject <IStorageMoverIdentity>`

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

`-DefaultProfile <PSObject>`

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

`-Break [<SwitchParameter>]`

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

`-HttpPipelineAppend <SendAsyncStep[]>`

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required?	false
Position?	named
Default value	False
Accept pipeline input?	false
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.PowerShell.Cmdlets.StorageMover.Models.IStorageMoverIdentity

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.StorageMover.Models.Api20231001.IJobRun

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help

[about_Hash_Tables](#).

INPUTOBJECT <IStorageMoverIdentity>: Identity Parameter

[AgentName <String>]: The name of the Agent resource.

[EndpointName <String>]: The name of the Endpoint resource.

[Id <String>]: Resource identity path

[JobDefinitionName <String>]: The name of the Job Definition resource.

[JobRunName <String>]: The name of the Job Run resource.

[ProjectName <String>]: The name of the Project resource.

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[StorageMoverName <String>]: The name of the Storage Mover resource.

[SubscriptionId <String>]: The ID of the target subscription.

----- EXAMPLE 1 -----

```
PS C:\>Get-AzStorageMoverJobRun -JobDefinitionName myJobDefinition -ResourceGroupName myResourceGroup  
-StorageMoverName myStorageMover -ProjectName myProject
```

----- EXAMPLE 2 -----

```
PS C:\>Get-AzStorageMoverJobRun -Name myJobRun -JobDefinitionName myJobDefinition -ResourceGroupName  
myResourceGroup -StorageMoverName myStorageMover -ProjectName  
myProject
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.storage/mover/get-azstoragemoverjobrun>

