



Windows PowerShell Get-Help on Cmdlet 'Get-AzSynapseLinkConnectionDetailedStatus'

PS:\>Get-HELP Get-AzSynapseLinkConnectionDetailedStatus -Full

NAME

Get-AzSynapseLinkConnectionDetailedStatus

SYNOPSIS

Gets detail status about a link connection in workspace.

SYNTAX

```

Get-AzSynapseLinkConnectionDetailedStatus [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name
<System.String> -WorkspaceName <System.String> [<CommonParameters>]

```

```

Get-AzSynapseLinkConnectionDetailedStatus [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name
<System.String> -WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace>
[<CommonParameters>]

```

DESCRIPTION

The Get-AzSynapseLinkConnectionDetailedStatus cmdlet gets detail status about a link connection in workspace. After

starting/stopping a link connection, you can use
this cmdlet to get the status of the link connection.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The Synapse link connection name for Azure Sql Database.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-WorkspaceName <System.String>

Name of Synapse workspace.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace>

workspace input object, usually passed through the pipeline.

Required?	true
Position?	named
Default value	None
Accept pipeline input?	True (ByValue)
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace

System.String

OUTPUTS

Microsoft.Azure.Commands.Synapse.Models.PSLinkConnectionDetailedStatus

NOTES

```
Get-AzSynapseLinkConnectionDetailedStatus -WorkspaceName ContosoWorkspace -Name ContosoLinkConnection
```

Gets detail status about link connection ContosoLinkConnection in the workspace ContosoWorkspace.

----- Example 2 -----

```
$ws = Get-AzSynapseWorkspace -Name ContosoWorkspace
```

```
$ws | Get-AzSynapseLinkConnectionDetailedStatus -Name ContosoLinkConnection
```

This command gets detail status about link connection ContosoLinkConnection under a workspace through pipeline.

----- Example 3 -----

```
Start-AzSynapseLinkConnection -WorkspaceName ContosoWorkspace -Name ContosoLinkConnection
```

```
Get-AzSynapseLinkConnectionDetailedStatus -WorkspaceName ContosoWorkspace -Name ContosoLinkConnection
```

Starts a link connection named ContosoLinkConnection in workspace ContosoWorkspace, it will cost some time to start, then you can call

Get-AzSynapseLinkConnectionDetailedStatus to monitor its status.

----- Example 4 -----

```
Stop-AzSynapseLinkConnection -WorkspaceName ContosoWorkspace -Name ContosoLinkConnection
```

```
Get-AzSynapseLinkConnectionDetailedStatus -WorkspaceName ContosoWorkspace -Name ContosoLinkConnection
```

Stops a link connection named ContosoLinkConnection in workspace ContosoWorkspace, it will cost some time from running to stop, then you can call

Get-AzSynapseLinkConnectionDetailedStatus to monitor its status.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.synapse/get-azsynapselinkconnectiondetailedstatus>