



Windows PowerShell Get-Help on Cmdlet 'Get-AzSynapseLinkConnectionLinkTable'

PS:\>Get-HELP Get-AzSynapseLinkConnectionLinkTable -Full

NAME

Get-AzSynapseLinkConnectionLinkTable

SYNOPSIS

Gets information about link tables under a link connection.

SYNTAX

Get-AzSynapseLinkConnectionLinkTable [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject

<Microsoft.Azure.Commands.Synapse.Models.PSLinkConnectionResource> [<CommonParameters>]

Get-AzSynapseLinkConnectionLinkTable [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -LinkConnectionName

<System.String> -WorkspaceName <System.String> [<CommonParameters>]

Get-AzSynapseLinkConnectionLinkTable [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -LinkConnectionName

<System.String> -WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace>

[<CommonParameters>]

DESCRIPTION

The Get-AzSynapseLinkConnectionLinkTable cmdlet gets information about link tables under a link connection.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Synapse.Models.PSLinkConnectionResource>

The information about the link connection.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-LinkConnectionName <System.String>

Name of link connection.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-WorkspaceName <System.String>

Name of Synapse workspace.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-WorkspaceObject <Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace>

workspace input object, usually passed through the pipeline.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Synapse.Models.PSSynapseWorkspace

Microsoft.Azure.Commands.Synapse.Models.PSLinkConnectionResource

OUTPUTS

Microsoft.Azure.Commands.Synapse.Models.PSLinkTableResource

NOTES

----- Example 1 -----

```
Get-AzSynapseLinkConnectionLinkTable -WorkspaceName ContosoWorkspace -LinkConnectionName  
ContosoLinkConnection
```

This command gets information about link tables under link connection ContosoLinkConnection in workspace ContosoWorkspace.

----- Example 2 -----

```
$ws = Get-AzSynapseWorkspace -Name ContosoWorkspace  
$ws | Get-AzSynapseLinkConnectionLinkTable -LinkConnectionName ContosoLinkConnection
```

This command gets information about link tables under link connection ContosoLinkConnection in workspace ContosoWorkspace through pipeline.

----- Example 3 -----

```
$lc = Get-AzSynapseLinkConnection -WorkspaceName ContosoWorkspace -Name ContosoLinkConnection  
$lc | Get-AzSynapseLinkConnectionLinkTable
```

This command gets information about link tables under a link connection through pipeline.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.synapse/get-azsynapselinkconnectionlinktable>