



Windows PowerShell Get-Help on Cmdlet 'Get-AzTenantBackfillStatus'

PS:\>Get-HELP Get-AzTenantBackfillStatus -Full

NAME

Get-AzTenantBackfillStatus

SYNOPSIS

Get the current Tenant Backfill Subscription Status

SYNTAX

```
Get-AzTenantBackfillStatus [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]  
[<CommonParameters>]
```

DESCRIPTION

The Get-AzTenantBackfillStatus gets the Backfill Status for the current Tenant

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

None

OUTPUTS

Microsoft.Azure.Commands.Resources.Models.ManagementGroups.PSBackfillStatus

NOTES

----- Example 1: Get the Backfill Tenant Status -----

Get-AzTenantBackfillStatus

Name : Completed

Type : c7a87cda-9a66-4920-b0f8-869baa04efe0

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.resources/get-aztenantbackfillstatus>