



**Full credit is given to all the above companies including the Operating System that this PDF file was generated!**

### ***Windows PowerShell Get-Help on Cmdlet 'Get-BCHashCache'***

**PS:\>Get-HELP Get-BCHashCache -Full**

#### **NAME**

Get-BCHashCache

#### **SYNOPSIS**

Retrieves the BranchCache hash cache.

#### **SYNTAX**

Get-BCHashCache [-AsJob] [-CimSession <CimSession[]>] [-ThrottleLimit <Int32>] [<CommonParameters>]

#### **DESCRIPTION**

The Get-BCHashCache cmdlet retrieves an object that represents the BranchCache hash cache.

#### **PARAMETERS**

**-AsJob** [<SwitchParameter>]

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete.

The cmdlet immediately returns an object that represents the job and then displays the command prompt. Page 101/141

continue to work in the session while the job

completes. To manage the job, use the `\*-Job` cmdlets. To get the job results, use the Receive-Job (<https://go.microsoft.com/fwlink/?LinkId=113372>) cmdlet.

For more information about Windows PowerShell background jobs, see [about\\_Jobs](#) (<https://go.microsoft.com/fwlink/?LinkId=113251>).

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

#### -CimSession <CimSession[]>

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a New-CimSession

(<https://go.microsoft.com/fwlink/?LinkId=227967>) or

[Get-CimSession] (<https://go.microsoft.com/fwlink/?LinkId=227966>) cmdlet. The default is the current session

on the local computer.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

#### -ThrottleLimit <Int32>

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of `0` is entered, then

Windows PowerShell calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are running on the computer. The throttle limit

applies only to the current cmdlet, not to the session or to the computer.

Required? false  
Position? named  
Default value None  
Accept pipeline input? False  
Accept wildcard characters? false

#### <CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkId=113216>).

#### INPUTS

None

#### OUTPUTS

Microsoft.Management.Infrastructure.CimInstance#root\StandardCimv2\MSFT\_NetBranchCacheHashCache

The `Microsoft.Management.Infrastructure.CimInstance` object is a wrapper class that displays Windows Management Instrumentation (WMI) objects. The path after the pound sign (`#`) provides the namespace and class name for the underlying WMI object.

#### NOTES

----- Example 1: Get the hash cache -----

PS C:\> Get-BCHashCache

This command retrieves the BranchCache hash cache.

## RELATED LINKS

Online

Version:

[https://learn.microsoft.com/powershell/module/branchcache/get-bchashcache?view=windowsserver2022-ps&wt.mc\\_id=ps-gethelp](https://learn.microsoft.com/powershell/module/branchcache/get-bchashcache?view=windowsserver2022-ps&wt.mc_id=ps-gethelp)

Disable-BC

Reset-BC