



Windows PowerShell Get-Help on Cmdlet 'Get-DtcTransactionsTraceSetting'

PS:\>Get-HELP Get-DtcTransactionsTraceSetting -Full

NAME

Get-DtcTransactionsTraceSetting

SYNOPSIS

Gets the DTC transactions trace setting of the host.

SYNTAX

Get-DtcTransactionsTraceSetting [-AsJob] [-CimSession <CimSession[]>] [-ThrottleLimit <Int32>]
[<CommonParameters>]

DESCRIPTION

The Get-DtcTransactionsTraceSetting cmdlet gets the Distributed Transaction Coordinator (DTC) transactions trace setting of the host. Trace settings are shared by all

DTC instances on a single host.

PARAMETERS

-AsJob [<SwitchParameter>]

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete.

The cmdlet immediately returns an object that represents the job and then displays the command prompt. You can continue to work in the session while the job

completes. To manage the job, use the ``*-Job`` cmdlets. To get the job results, use the `Receive-Job` (<https://go.microsoft.com/fwlink/?LinkID=113372>) cmdlet.

For more information about Windows PowerShell background jobs, see `about_Jobs` (<https://go.microsoft.com/fwlink/?LinkID=113251>).

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

`-CimSession <CimSession[]>`

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a `New-CimSession`

(<https://go.microsoft.com/fwlink/p/?LinkId=227967>) or

`[Get-CimSession]`(<https://go.microsoft.com/fwlink/p/?LinkId=227966>) cmdlet. The default is the current session on the local computer.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

`-ThrottleLimit <Int32>`

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of ``0`` is entered, then

Windows PowerShell calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are

running on the computer. The throttle limit

applies only to the current cmdlet, not to the session or to the computer.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

DtcTransactionsTraceSettings

This cmdlet returns an object of DtcTransactionsTraceSettings containing the trace settings information.

NOTES

----- Example 1: Get DTC transactions trace setting -----

```
PS C:\> Get-DtcTransactionsTraceSetting
```

```
AbortedTransactionsTracingEnabled AllTransactionsTracingEnabled LongLivedTransactionsTracingEnabled
```

```
PSComputerName
```

True

False

True

This command queries the transactions trace setting on the local host.

RELATED LINKS

Online

Version:

https://learn.microsoft.com/powershell/module/msdtc/get-dtctransactionstracesetting?view=windowsserver2022-ps&wt.mc_id=ps-gethelp

Set-DtcTransactionsTraceSetting