



### ***Windows PowerShell Get-Help on Cmdlet 'Get-NetAdapterStatistics'***

***PS:\>Get-HELP Get-NetAdapterStatistics -Full***

#### **NAME**

Get-NetAdapterStatistics

#### **SYNOPSIS**

Gets statistics from a network adapter.

#### **SYNTAX**

Get-NetAdapterStatistics [-AsJob] [-CimSession <CimSession[]>] [-IncludeHidden] -InterfaceDescription <String[]>  
[-ThrottleLimit <Int32>] [<CommonParameters>]

Get-NetAdapterStatistics [[-Name] <String[]>] [-AsJob] [-CimSession <CimSession[]>] [-IncludeHidden] [-ThrottleLimit  
<Int32>] [<CommonParameters>]

#### **DESCRIPTION**

The Get-NetAdapterStatistics cmdlet gets networking statistics from a network adapter. The statistics include broadcast, multicast, discards, and errors.

## PARAMETERS

### -AsJob [<SwitchParameter>]

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete. The cmdlet immediately returns an object that

represents the job and then displays the command prompt. You can continue to work in the session while the job completes. To manage the job, use the ``*-Job``

cmdlets. To get the job results, use the `Receive-Job` (<https://go.microsoft.com/fwlink/?LinkID=113372>) cmdlet. For more information about Windows PowerShell

background jobs, see `about_Jobs` (<https://go.microsoft.com/fwlink/?LinkID=113251>).

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

### -CimSession <CimSession[]>

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a `New-CimSession`

(<https://go.microsoft.com/fwlink/p/?LinkId=227967>) or

`[Get-CimSession]`(<https://go.microsoft.com/fwlink/p/?LinkId=227966>) cmdlet. The default is the current session on the local computer.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

### -IncludeHidden [<SwitchParameter>]

Indicates that the cmdlet includes both visible and hidden network adapters in the operation. By default only visible network adapters are included. If a wildcard

character is used in identifying a network adapter and this parameter has been specified, then the wildcard string is

matched against both hidden and visible

network adapters.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

#### **-InterfaceDescription <String[]>**

Specifies an array of network adapter interface descriptions. For a physical network adapter this is typically the name of the vendor of the network adapter

followed by a part number and description, such as `Contoso 12345 Gigabit Network Device`.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

#### **-Name <String[]>**

Specifies an array of network adapter names.

Required? false

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

#### **-ThrottleLimit <Int32>**

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of `0` is entered, then

Windows PowerShell calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are

running on the computer. The throttle limit

applies only to the current cmdlet, not to the session or to the computer.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

#### <CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

#### INPUTS

None

#### OUTPUTS

Microsoft.Management.Infrastructure.CimInstance#ROOT/StandardCimv2/MSFT\_NetAdapterStatisticsSettingData

The `Microsoft.Management.Infrastructure.CimInstance` object is a wrapper class that displays Windows Management Instrumentation (WMI) objects. The path after the pound sign (`#`) provides the namespace and class name for the underlying WMI object.

#### NOTES

```
PS C:\> Get-NetAdapterStatistics -Name "MyAdapter"
```

This command displays statistics for the network adapter named MyAdapter.

Example 2: Display all statistics for the specified network adapter

```
PS C:\> Get-NetAdapterStatistics -Name "MyAdapter" | Format-List -Property "**"
```

This command displays all statistics for the network adapter named MyAdapter.

## RELATED LINKS

Online

Version:

[https://learn.microsoft.com/powershell/module/netadapter/get-netadapterstatistics?view=windowsserver2022-ps&wt.mc\\_id=ps-gethelp](https://learn.microsoft.com/powershell/module/netadapter/get-netadapterstatistics?view=windowsserver2022-ps&wt.mc_id=ps-gethelp)