



***Windows PowerShell Get-Help on Cmdlet 'Get-PhysicalExtent'***

***PS:\>Get-HELP Get-PhysicalExtent -Full***

NAME

Get-PhysicalExtent

SYNTAX

Get-PhysicalExtent -VirtualDisk <CimInstance#MSFT\_VirtualDisk> [-CimSession <CimSession>]

[<CommonParameters>]

Get-PhysicalExtent -StorageTier <CimInstance#MSFT\_StorageTier> [-CimSession <CimSession>]

[<CommonParameters>]

Get-PhysicalExtent -PhysicalDisk <CimInstance#MSFT\_PhysicalDisk> [-CimSession <CimSession>]

[<CommonParameters>]

PARAMETERS

-CimSession <CimSession>

Required? false

Position? Named

Accept pipeline input? false

Parameter set name (All)

Aliases None

Dynamic? false

-PhysicalDisk <CimInstance#MSFT\_PhysicalDisk>

Required? true

Position? Named

Accept pipeline input? true (ByValue)

Parameter set name ByPhysicalDisk

Aliases None

Dynamic? false

-StorageTier <CimInstance#MSFT\_StorageTier>

Required? true

Position? Named

Accept pipeline input? true (ByValue)

Parameter set name ByStorageTier

Aliases None

Dynamic? false

-VirtualDisk <CimInstance#MSFT\_VirtualDisk>

Required? true

Position? Named

Accept pipeline input? true (ByValue)

Parameter set name ByVirtualDisk

Aliases None

Dynamic? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,  
OutBuffer, PipelineVariable, and OutVariable. For more information, see  
about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

## INPUTS

Microsoft.Management.Infrastructure.CimInstance

## OUTPUTS

System.Object

## ALIASES

None

## REMARKS

Get-Help cannot find the Help files for this cmdlet on this computer. It is displaying only partial help.

-- To download and install Help files for the module that includes this cmdlet, use Update-Help.