



python



PowerShell

FPDF Library
PDF generator

Full credit is given to the above companies including the OS that this PDF file was generated!

PowerShell Get-Help on command 'Get-UevConfiguration'

PS C:\Users\wahid> Get-Help Get-UevConfiguration

NAME

Get-UevConfiguration

SYNOPSIS

Gets the UE-V configuration settings.

SYNTAX

Get-UevConfiguration -Computer [<CommonParameters>]

Get-UevConfiguration -CurrentComputerUser [<CommonParameters>]

Get-UevConfiguration -Details [<CommonParameters>]

DESCRIPTION

The Get-UevConfiguration cmdlet gets the Microsoft User Experience Virtualization (UE-V) configuration settings. If you specify the Computer parameter, the cmdlet gets the settings for all users on the computer. If you specify the CurrentComputerUser parameter, the cmdlet gets the settings for just the current user.

PARAMETERS

-Computer [<SwitchParameter>]

Indicates that the cmdlet gets the UE-V configuration settings for all users on the computer.

-CurrentComputerUser [<SwitchParameter>]

Indicates that the cmdlet gets the UE-V configuration settings for the current user only.

-Details [<SwitchParameter>]

Indicates that the cmdlet gets the UE-V configuration settings, including all of the details.

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

----- Example 1: Get the uev_tla configuration -----

PS C:\> Get-UevConfiguration

Key	Value
---	----
MaxPackageSizeInBytes	700000
SettingsImportNotifyDelayInSeconds	10
SettingsImportNotifyEnabled	False
SettingsStoragePath	\\\\$ServerName\\Path\\To\\CentralStore
SettingsTemplateCatalogPath	

SyncEnabled	True
SyncMethod	OfflineFiles
SyncFromRepositoryTimeoutInMilliseconds	2000

This command gets the active UE-V configuration on the computer where you run the cmdlet.

----- Example 2: Get the computer-wide configuration -----

```
PS C:\> Get-UevConfiguration -Computer
```

Key	Value
---	----
MaxPackageSizeInBytes	700000
SettingsImportNotifyDelayInSeconds	
SettingsImportNotifyEnabled	
SettingsStoragePath	\ServerName\Path\To\CentralStore
SettingsTemplateCatalogPath	
SyncEnabled	
SyncMethod	OfflineFiles
SyncFromRepositoryTimeoutInMilliseconds	2000

This command gets the UE-V configuration settings for all users on the computer. The command gets the HKey Local Machine (HKLM) configuration settings that are in the registry.

----- Example 3: Get the user-specific configuration -----

```
PS C:\> Get-UevConfiguration -CurrentComputerUser
```

Key	Value
---	----
MaxPackageSizeInBytes	

SettingsImportNotifyDelayInSeconds
SettingsImportNotifyEnabled
SettingsStoragePath
SyncEnabled
SyncMethod
SyncFromRepositoryTimeoutInMilliseconds

This command gets the user-specific UE-V configuration, including the HKey Current User (HKCU) configuration settings that are in the registry.

REMARKS

To see the examples, type: "get-help Get-UevConfiguration -examples".
For more information, type: "get-help Get-UevConfiguration -detailed".
For technical information, type: "get-help Get-UevConfiguration -full".
For online help, type: "get-help Get-UevConfiguration -online"