



Windows PowerShell Get-Help on Cmdlet 'Invoke-AzSqlElasticPoolFailover'

PS:\>Get-HELP Invoke-AzSqlElasticPoolFailover -Full

NAME

Invoke-AzSqlElasticPoolFailover

SYNOPSIS

Failovers an elastic pool.

SYNTAX

```
Invoke-AzSqlElasticPoolFailover [-ResourceGroupName] <System.String> [-ServerName] <System.String>
[-ElasticPoolName] <System.String> [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Invoke-AzSqlElasticPoolFailover cmdlet failovers an elastic pool. Failover will occur on all databases in the elastic pool after running this cmdlet.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ElasticPoolName <System.String>

The name of the Azure SQL Elastic Pool to remove.

Required? true

Position? 2

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Skip confirmation message for performing the action

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

On Successful execution, returns true. By default, this cmdlet does not generate any output.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

The name of the resource group.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ServerName <System.String>

The name of the Azure SQL Server the Elastic Pool is in.

Required? true

Position? 1

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.String

OUTPUTS

NOTES

----- Example 1 -----

```
Invoke-AzSqlElasticPoolFailover -ResourceGroupName "ResourceGroup01" -ServerName "Server01" -ElasticPoolName "ElasticPool01"
```

This command will failover the elastic pool named "ElasticPool01" on the server named "Server01". This means failover will occur on all databases in the elastic pool named "ElasticPool01".

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.sql/invoke-azsqlelasticpoolfailover>

[Get-AzSqlElasticPool](#)

[Get-AzSqlElasticPoolActivity](#)

[Get-AzSqlElasticPoolDatabase](#)

[Invoke-AzSqlDatabaseFailover](#)

[New-AzSqlElasticPool](#)

[Remove-AzSqlElasticPool](#)

[Set-AzSqlElasticPool](#)

SQL Database Documentation <https://learn.microsoft.com/azure/sql-database/>