



Windows PowerShell Get-Help on Cmdlet 'New-AzContainerInstanceInitDefinitionObject'

PS:\>Get-HELP New-AzContainerInstanceInitDefinitionObject -Full

NAME

New-AzContainerInstanceInitDefinitionObject

SYNOPSIS

Create a in-memory object for InitContainerDefinition

SYNTAX

```
New-AzContainerInstanceInitDefinitionObject -Name <String> [-Command <String[]>] [-EnvironmentVariable  
<IEnvironmentVariable[]>] [-Image <String>] [-VolumeMount  
<IVolumeMount[]>] [<CommonParameters>]
```

DESCRIPTION

Create a in-memory object for InitContainerDefinition

PARAMETERS

-Name <String>

The name for the init container.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Command <String[]>

The command to execute within the init container in exec form.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-EnvironmentVariable <IEnvironmentVariable[]>

The environment variables to set in the init container.

To construct, see NOTES section for ENVIRONMENTVARIABLE properties and create a hash table.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Image <String>

The image of the init container.

Required? false
Position? named
Default value
Accept pipeline input? false

Accept wildcard characters? false

-VolumeMount <IVolumeMount[]>

The volume mounts available to the init container.

To construct, see NOTES section for VOLUMEMOUNT properties and create a hash table.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see

about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.ContainerInstance.Models.Api20221001Preview.InitContainerDefinition

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help

about_Hash_Tables.

ENVIRONMENTVARIABLE <IEnvironmentVariable[]>: The environment variables to set in the init container.

Name <String>: The name of the environment variable.

[SecureValue <String>]: The value of the secure environment variable.

[Value <String>]: The value of the environment variable.

VOLUMEMOUNT <IVolumeMount[]>: The volume mounts available to the init container.

MountPath <String>: The path within the container where the volume should be mounted. Must not contain colon (:).

Name <String>: The name of the volume mount.

[ReadOnly <Boolean?>]: The flag indicating whether the volume mount is read-only.

----- EXAMPLE 1 -----

```
PS C:\>New-AzContainerInstanceInitDefinitionObject -Name "initDefinition" -Command "/bin/sh -c myscript.sh"
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.ContainerInstance/new-AzContainerInstanceInitDefinitionObject>