



Windows PowerShell Get-Help on Cmdlet 'New-AzDataBricksAccessConnector'

PS:\>Get-HELP New-AzDataBricksAccessConnector -Full

NAME

New-AzDataBricksAccessConnector

SYNOPSIS

Creates or updates azure databricks accessConnector.

SYNTAX

```
New-AzDataBricksAccessConnector -Name <String> -ResourceGroupName <String> [-SubscriptionId <String>] -Location  
<String> [-IdentityType <ManagedServiceIdentityType>]  
[-Tag <Hashtable>] [-UserAssignedIdentity <Hashtable>] [-DefaultProfile <PSObject>] [-AsJob] [-Break]  
[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend  
<SendAsyncStep[]>] [-NoWait] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf]  
[-Confirm] [<CommonParameters>]
```

DESCRIPTION

Creates or updates azure databricks accessConnector.

PARAMETERS

-Name <String>

The name of the azure databricks accessConnector.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Location <String>

The geo-location where the resource lives

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-IdentityType <ManagedServiceIdentityType>

Type of managed service identity (where both SystemAssigned and UserAssigned types are allowed).

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Tag <Hashtable>

Resource tags.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-UserAssignedIdentity <Hashtable>

The set of user assigned identities associated with the resource.

The userAssignedIdentities dictionary keys will be ARM resource ids in the form:

`/subscriptions/{subscriptionId}/resourceGroups/{resourceGroupName}/providers/Microsoft.ManagedIdentity/userAssignedIdentities/{identityName}.`

The dictionary values can be empty objects ({}) in requests.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-DefaultProfile <PSObject>

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-AsJob [<SwitchParameter>]

Run the command as a job

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-NoWait [<SwitchParameter>]

Run the command asynchronously

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Databricks.Models.Api20230501.IAccessConnector

----- EXAMPLE 1 -----

```
PS C:\>New-AzDatabricksAccessConnector -ResourceGroupName azps_test_gp_db -Name  
azps-databricks-accessconnector -Location eastus -IdentityType 'SystemAssigned'
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.databricks/new-azdatabricksaccessconnector>