



Windows PowerShell Get-Help on Cmdlet 'New-AzMigrateDiskMapping'

PS:\>Get-HELP New-AzMigrateDiskMapping -Full

NAME

New-AzMigrateDiskMapping

SYNOPSIS

Creates a new disk mapping

SYNTAX

New-AzMigrateDiskMapping -DiskID <String> -IsOSDisk <String> -DiskType <String> [-DiskEncryptionSetID <String>]
[<CommonParameters>]

DESCRIPTION

The New-AzMigrateDiskMapping cmdlet creates a mapping of the source disk attached to the server to be migrated

PARAMETERS

-DiskID <String>

Specifies the disk ID of the disk attached to the discovered server to be migrated.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-IsOSDisk <String>

Specifies whether the disk contains the Operating System for the source server to be migrated.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-DiskType <String>

Specifies the type of disks to be used for the Azure VM.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-DiskEncryptionSetID <String>

Specifies the disk encryption set to be used.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Migrate.Models.Api202301.IVMwareCbtDiskInput

----- EXAMPLE 1 -----

```
PS C:\>New-AzMigrateDiskMapping -DiskID a -DiskType Standard -IsOSDisk 'true'
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.migrate/new-azmigratediskmapping>