



Windows PowerShell Get-Help on Cmdlet 'New-AzMigrateHCIDiskMappingObject'

PS:\>Get-HELP New-AzMigrateHCIDiskMappingObject -Full

NAME

New-AzMigrateHCIDiskMappingObject

SYNOPSIS

Creates a new disk mapping

SYNTAX

New-AzMigrateHCIDiskMappingObject -DiskID <String> -IsOSDisk <String> -IsDynamic <String> -Size <Int64> -Format
<String> [<CommonParameters>]

DESCRIPTION

The New-AzMigrateHCIDiskMappingObject cmdlet creates a mapping of the source disk attached to the server to be migrated

PARAMETERS

-DiskID <String>

Specifies the disk ID of the disk attached to the discovered server to be migrated.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-IsOSDisk <String>

Specifies whether the disk contains the Operating System for the source server to be migrated.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-IsDynamic <String>

Specifies whether the disk is dynamic.

Required? true
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-Size <Int64>

Specifies the disk size in GB.

Required? true
Position? named
Default value 0
Accept pipeline input? false
Accept wildcard characters? false

-Format <String>

Specifies the disk format.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Migrate.Models.Api20210216Preview.AzStackHCIDiskInput

----- EXAMPLE 1 -----

```
PS C:\>New-AzMigrateHCIDiskMappingObject -DiskID a -IsOSDisk true -IsDynamic true -Size 1 -Format VHDX
```

