



Windows PowerShell Get-Help on Cmdlet 'New-AzSecurityConnectorActionableRemediationObject'

PS:\>Get-HELP New-AzSecurityConnectorActionableRemediationObject -Full

NAME

New-AzSecurityConnectorActionableRemediationObject

SYNOPSIS

Create an in-memory object for ActionableRemediation.

SYNTAX

```
New-AzSecurityConnectorActionableRemediationObject [-BranchConfiguration <ITargetBranchConfiguration>]
[-CategoryConfiguration <ICategoryConfiguration[]>]
[-InheritFromParentState <String>] [-State <String>] [<CommonParameters>]
```

DESCRIPTION

Create an in-memory object for ActionableRemediation.

PARAMETERS

-BranchConfiguration <ITargetBranchConfiguration>
Repository branch configuration for PR Annotations.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-CategoryConfiguration <ICategoryConfiguration[]>

Gets or sets list of categories and severity levels.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-InheritFromParentState <String>

Update Settings.

Enabled - Resource should inherit configurations from parent.

Disabled - Resource should not inherit configurations from parent.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-State <String>

ActionableRemediation Setting.

None - the setting was never set.

Enabled - ActionableRemediation is enabled.

Disabled - ActionableRemediation is disabled.

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

OUTPUTS

Microsoft.Azure.PowerShell.Cmdlets.Security.Models.ActionableRemediation

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help

[about_Hash_Tables](#).

BRANCHCONFIGURATION <ITargetBranchConfiguration>: Repository branch configuration for PR Annotations.

[AnnotateDefaultBranch <String>]: Configuration of PR Annotations on default branch. Enabled - PR Annotations are enabled on the resource's default

branch. Disabled - PR Annotations are disabled on the resource's default branch.

[BranchName <List<String>>]: Gets or sets branches that should have annotations.

CATEGORYCONFIGURATION <ICategoryConfiguration[]>: Gets or sets list of categories and severity levels.

[Category <String>]: Rule categories. Code - code scanning results. Artifact scanning results.

Dependencies scanning results.

IaC results. Secrets scanning results. Container scanning results.

[MinimumSeverityLevel <String>]: Gets or sets minimum severity level for a given category.

----- EXAMPLE 1 -----

```
PS C:\>New-AzSecurityConnectorActionableRemediationObject -State Enabled -InheritFromParentState Disabled `
```

```
-BranchConfiguration @{AnnotateDefaultBranch="Enabled"; branchName=@("main", "hotfix")} -CategoryConfiguration  
@( @{category="First"; minimumSeverityLevel="High"},  
  @{category="Second"; minimumSeverityLevel="Low"})
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/Az.Security/new-azsecurityconnectoractionableremediationobject>