



Full credit is given to all the above companies including the Operating System that this PDF file was generated!

Windows PowerShell Get-Help on Cmdlet 'Remove-AutologgerConfig'

PS:\>Get-HELP Remove-AutologgerConfig -Full

NAME

Remove-AutologgerConfig

SYNOPSIS

Removes the named AutoLogger session configuration from the registry.

SYNTAX

```
Remove-AutologgerConfig [-AsJob] [-CimSession <CimSession[]>] [-Confirm] -InputObject <CimInstance[]> [-PassThru]
[-ThrottleLimit <Int32>] [-WhatIf]
[<CommonParameters>]
```

```
Remove-AutologgerConfig [-Name] <String[]> [-AsJob] [-CimSession <CimSession[]>] [-Confirm] [-PassThru]
[-ThrottleLimit <Int32>] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Remove-AutologgerConfig cmdlet removes the named AutoLogger session configuration from the registry.

PARAMETERS

-AsJob [<SwitchParameter>]

Runs the cmdlet as a background job. Use this parameter to run commands that take a long time to complete.

The cmdlet immediately returns an object that represents the job and then displays the command prompt. You can continue to work in the session while the job

completes. To manage the job, use the `*-Job` cmdlets. To get the job results, use the Receive-Job
(<https://go.microsoft.com/fwlink/?LinkId=113372>) cmdlet.

For more information about Windows PowerShell background jobs, see about_Jobs
(<https://go.microsoft.com/fwlink/?LinkId=113251>).

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-CimSession <CimSession[]>

Runs the cmdlet in a remote session or on a remote computer. Enter a computer name or a session object, such as the output of a New-CimSession

(<https://go.microsoft.com/fwlink/p/?LinkId=227967>)

or

[Get-CimSession] (<https://go.microsoft.com/fwlink/p/?LinkId=227966>) cmdlet. The default is the current session

on the local computer.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Prompts you for confirmation before running the cmdlet.

Page 2/5

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-InputObject <CimInstance[]>

Specifies the input to this cmdlet. You can use this parameter, or you can pipe the input to this cmdlet.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Name <String[]>

Specifies the name of the AutoLogger session.

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-PassThru [<SwitchParameter>]

Indicates that this cmdlet returns an object that represents the item on which it operates. By default, this cmdlet does not generate any output.

Required? false
Position? named
Default value False
Accept pipeline input? False

Accept wildcard characters? false

-ThrottleLimit <Int32>

Specifies the maximum number of concurrent operations that can be established to run the cmdlet. If this parameter is omitted or a value of `0` is entered, then

Windows PowerShell calculates an optimum throttle limit for the cmdlet based on the number of CIM cmdlets that are running on the computer. The throttle limit

applies only to the current cmdlet, not to the session or to the computer.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkId=113216>).

INPUTS

OUTPUTS

NOTES

----- Example 1: Remove an AutoLogger configuration -----

```
PS C:\> Remove-AutologgerConfig -Name "WDIContextLog"
```

This command removes an AutoLogger configuration named WDIContextLog.

RELATED LINKS

Online

Version:

https://learn.microsoft.com/powershell/module/eventtracingmanagement/remove-autologgerconfig?view=windowsserver2022-ps&wt.mc_id=ps-gethelp

Configuring and Starting an AutoLogger Session <https://msdn.microsoft.com/library/windows/desktop/aa363687.aspx>

Logging Mode Constants <https://msdn.microsoft.com/library/windows/desktop/aa364080.aspx>

WNODE_HEADER structure <https://msdn.microsoft.com/library/windows/desktop/aa364160.aspx>

Get-AutologgerConfig

New-AutologgerConfig

Update-AutologgerConfig