



## ***Windows PowerShell Get-Help on Cmdlet 'Remove-AzAutoscaleSetting'***

***PS:\>Get-HELP Remove-AzAutoscaleSetting -Full***

### NAME

Remove-AzAutoscaleSetting

### SYNOPSIS

Deletes and autoscale setting

### SYNTAX

Remove-AzAutoscaleSetting -Name <String> -ResourceGroupName <String> [-SubscriptionId <String>] [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend

<SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-PassThru] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf]

[-Confirm] [<CommonParameters>]

Remove-AzAutoscaleSetting -InputObject <IAutoscaleIdentity> [-DefaultProfile <PSObject>] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend

<SendAsyncStep[]>] [-PassThru] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]

## DESCRIPTION

Deletes and autoscale setting

## PARAMETERS

-Name <String>

The autoscale setting name.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

#### **-InputObject <IAutoscaleIdentity>**

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

#### **-DefaultProfile <PSObject>**

The DefaultProfile parameter is not functional.

Use the SubscriptionId parameter when available if executing the cmdlet against a different subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

#### **-Break [<SwitchParameter>]**

Wait for .NET debugger to attach

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

#### **-HttpPipelineAppend <SendAsyncStep[]>**

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false

Position?                named  
Default value  
Accept pipeline input?    false  
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required?                false  
Position?                named  
Default value  
Accept pipeline input?    false  
Accept wildcard characters? false

-PassThru [<SwitchParameter>]

Returns true when the command succeeds

Required?                false  
Position?                named  
Default value            False  
Accept pipeline input?    false  
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required?                false  
Position?                named  
Default value  
Accept pipeline input?    false  
Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

#### -ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

#### -WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

#### -Confirm [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

## <CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about\\_CommonParameters](https://go.microsoft.com/fwlink/?LinkID=113216) (<https://go.microsoft.com/fwlink/?LinkID=113216>).

## INPUTS

Microsoft.Azure.PowerShell.Cmdlets.Monitor.Autoscale.Models.IAutoscaleIdentity

## OUTPUTS

System.Boolean

## NOTES

### COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help

[about\\_Hash\\_Tables](#).

INPUTOBJECT <IAutoscaleIdentity>: Identity Parameter

[AutoscaleSettingName <String>]: The autoscale setting name.

[Id <String>]: Resource identity path

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[SubscriptionId <String>]: The ID of the target subscription.

----- EXAMPLE 1 -----

PS C:\>Remove-AzAutoscaleSetting -Name test-autoscalesetting -ResourceGroupName test-group

#### RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.monitor/remove-azautoscalesetting>