



Windows PowerShell Get-Help on Cmdlet 'Remove-AzDataBoxEdgeShare'

PS:\>Get-HELP Remove-AzDataBoxEdgeShare -Full

NAME

Remove-AzDataBoxEdgeShare

SYNOPSIS

Removes a share from the device.

SYNTAX

```
Remove-AzDataBoxEdgeShare [-ResourceGroupName] <System.String> [-DeviceName] <System.String> [-Name]
<System.String> [-AsJob] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

```
Remove-AzDataBoxEdgeShare [-ResourceId] <System.String> [-AsJob] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

```
Remove-AzDataBoxEdgeShare [-ResourceId] <System.String> [-AsJob] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru]
```

[-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

The Remove-AzDataBoxEdgeEdgeShare cmdlet removes the associated edge shares for a Data Box Edge device.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DeviceName <System.String>

Device Name

Required? true

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeShare>

Input Object

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

Resource Name

Required? true

Position? 2

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

returns true if successful

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Resource Group Name

Required? true

Position? 0
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-ResourceId <System.String>

Azure ResourceId

Required? true
Position? 0
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

System.String

Microsoft.Azure.PowerShell.Cmdlets.DataBoxEdge.Models.PSDataBoxEdgeShare

OUTPUTS

System.Boolean

NOTES

----- Example 1 -----

Remove-AzDataBoxEdgeShare -ResourceGroupName resourceGroupName -DeviceName deviceName -Name shareName

