



Full credit is given to all the above companies including the Operating System that this PDF file was generated!

Windows PowerShell Get-Help on Cmdlet 'Remove-AzHDInsightClusterAutoscaleConfiguration'

PS:\>Get-HELP Remove-AzHDInsightClusterAutoscaleConfiguration -Full

NAME

Remove-AzHDInsightClusterAutoscaleConfiguration

SYNOPSIS

Removes the autoscale configuration of the HDInsight cluster.

SYNTAX

```
Remove-AzHDInsightClusterAutoscaleConfiguration [[-ResourceGroupName] <System.String>] [-ClusterName]
<System.String> [-AsJob] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

```
Remove-AzHDInsightClusterAutoscaleConfiguration [-InputObject]
<Microsoft.Azure.Commands.HDInsight.Models.AzureHDInsightCluster> [-AsJob] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

```
Remove-AzHDInsightClusterAutoscaleConfiguration [-ResourceId] <System.String> [-AsJob] [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Confirm] [-WhatIf]
```

[<CommonParameters>]

DESCRIPTION

The Remove-AzHDInsightClusterAutoscaleConfiguration cmdlet removes the autoscale configuration of the HDInsight cluster.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-ClusterName <System.String>

Gets or sets the name of the cluster.

Required? true

Position? 1

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.HDInsight.Models.AzureHDInsightCluster>

Gets or sets the input object.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-ResourceGroupName <System.String>

Gets or sets the name of the resource group.

Required? false

Position? 0

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceId <System.String>

Gets or sets the resource id.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkId=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.HDInsight.Models.AzureHDInsightCluster

OUTPUTS

System.Boolean

NOTES

Example 1: Remove the autoscale configuration of the HDInsight cluster.

```
$clusterResourceGroup="group"  
$clusterName="MyCluster"  
  
Remove-AzHDInsightClusterAutoscaleConfiguration -ResourceGroupName $clusterResourceGroup -ClusterName  
$clusterName
```

This command removes the autoscale configuration of the HDInsight cluster.

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.hdinsight/remove-azhdinsightclusterautoscaleconfiguration>

New-AzHDInsightClusterAutoscaleConfiguration

Set-AzHDInsightClusterAutoscaleConfiguration

Get-AzHDInsightClusterAutoscaleConfiguration