



Windows PowerShell Get-Help on Cmdlet 'Remove-AzKeyVaultCertificateIssuer'

PS: \>Get-HELP Remove-AzKeyVaultCertificateIssuer -Full

NAME

Remove-AzKeyVaultCertificateIssuer

SYNOPSIS

Deletes a certificate issuer from a key vault.

SYNTAX

```
Remove-AzKeyVaultCertificateIssuer [-InputObject]
<Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateIssuerIdentityItem> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]

Remove-AzKeyVaultCertificateIssuer [-VaultName] <System.String> [-Name] <System.String> [-DefaultProfile
    <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Remove-AzKeyVaultCertificateIssuer cmdlet deletes a certificate issuer from a key vault.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Forces the command to run without asking for user confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateIssuerIdentityItem>

Certificate Issuer Object

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the issuer to remove.

Required?	true
Position?	1
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-PassThru <System.Management.Automation.SwitchParameter>

Returns an object representing the item with which you are working. By default, this cmdlet does not generate any output.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-VaultName <System.String>

Specifies the name of a key vault.

Required?	true
Position?	0
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run. Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateIssuerIdentityItem

OUTPUTS

Microsoft.Azure.Commands.KeyVault.Models.PSKeyVaultCertificateIssuer

NOTES

```
Remove-AzKeyVaultCertificateIssuer -VaultName "ContosoKV01" -Name "TestIssuer01" -Force
```

AccountId :

ApiKey :

OrganizationDetails :

Name : TestIssuer01

IssuerProvider : test

VaultName : ContosoKV01

This command removes the certificate issuer named TestIssuer01 from the ContosoKV01 key vault.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.keyvault/remove-azkeyvaultcertificateissuer>

Get-AzKeyVaultCertificateIssuer

Set-AzKeyVaultCertificateIssuer