



Windows PowerShell Get-Help on Cmdlet 'Remove-AzLoadBalancerBackendAddressPool'

PS:\>Get-HELP Remove-AzLoadBalancerBackendAddressPool -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Remove-AzLoadBalancerBackendAddressPool

SYNOPSIS

Removes a backend pool from a load balancer

SYNTAX

```

Remove-AzLoadBalancerBackendAddressPool [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
<Microsoft.Azure.Commands.Network.Models.PSBackendAddressPool> [-LoadBalancerName <System.String>]
[-PassThru] [-Confirm] [-WhatIf] [<CommonParameters>]

```

```

Remove-AzLoadBalancerBackendAddressPool [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -LoadBalancer
<Microsoft.Azure.Commands.Network.Models.PSLoadBalancer> [-LoadBalancerName <System.String>]

```

<System.String> [-PassThru] [-Confirm] [-WhatIf]

[<CommonParameters>]

Remove-AzLoadBalancerBackendAddressPool

[-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-LoadBalancerName

<System.String>] -Name <System.String> [-PassThru] -ResourceGroupName <System.String> [-Confirm] [-WhatIf]

[<CommonParameters>]

Remove-AzLoadBalancerBackendAddressPool

[-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-LoadBalancerName

<System.String>] [-PassThru] -ResourceId <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

Removes a backend pool from a load balancer

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Network.Models.PSBackendAddressPool>

The backend address pool to remove

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-LoadBalancer <Microsoft.Azure.Commands.Network.Models.PSLoadBalancer>

The load balancer resource.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-LoadBalancerName <System.String>

The name of the load balancer.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The name of the load balancer.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

{{ Fill PassThru Description }}

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource group name of the load balancer.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-ResourceId <System.String>

Required? true
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.Network.Models.PSLoadBalancer

System.String

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSBackendAddressPool

NOTES

----- Example 1 -----

##removing by passing lb object via pipeline

```
$lb | Remove-AzLoadBalancerBackendAddressPool -Name $backendPool1
```

----- Example 2 -----

##removing by passing input object

```
Remove-AzLoadBalancerBackendAddressPool -InputObject $backendPoolObject
```

----- Example 3 -----

##removing by passing input object

```
Remove-AzLoadBalancerBackendAddressPool -ResourceId $backendPoolObject.Id
```

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/remove-azloadbalancerbackendaddresspool>