



Full credit is given to all the above companies including the Operating System that this PDF file was generated!

Windows PowerShell Get-Help on Cmdlet 'Remove-AzLoadBalancerInboundNatPoolConfig'

PS:\>Get-HELP Remove-AzLoadBalancerInboundNatPoolConfig -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Remove-AzLoadBalancerInboundNatPoolConfig

SYNOPSIS

Removes an inbound NAT pool configuration from a load balancer.

SYNTAX

Remove-AzLoadBalancerInboundNatPoolConfig [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer> -LoadBalancer

<Microsoft.Azure.Commands.Network.Models.PSLoadBalancer> [-Name <System.String>] [-Confirm] [-WhatIf]

[<CommonParameters>]

DESCRIPTION

The Remove-AzLoadBalancerInboundNatPoolConfig cmdlet removes an inbound NAT pool configuration from a load balancer.

balancer.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-LoadBalancer <Microsoft.Azure.Commands.Network.Models.PSLoadBalancer>

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName, ByValue)

Accept wildcard characters? false

-Name <System.String>

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkId=113216>).

INPUTS

Microsoft.Azure.Commands.Network.Models.PSLoadBalancer

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSLoadBalancer

NOTES

----- 1: Remove -----

```
$slb = Get-AzLoadBalancer -Name "MyLoadBalancer" -ResourceGroupName "MyResourceGroup"  
Remove-AzLoadBalancerInboundNatPoolConfig -Name myinboundnatpool -LoadBalancer $slb
```

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/remove-azloadbalancerinboundnatpoolconfig>
[Add-AzLoadBalancerInboundNatPoolConfig](#)
[Get-AzLoadBalancerInboundNatPoolConfig](#)
[New-AzLoadBalancerInboundNatPoolConfig](#)
[Set-AzLoadBalancerInboundNatPoolConfig](#)