



Windows PowerShell Get-Help on Cmdlet 'Remove-AzNetworkInterfaceTapConfig'

PS: \>Get-HELP Remove-AzNetworkInterfaceTapConfig -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Remove-AzNetworkInterfaceTapConfig

SYNOPSIS

Removes a tap configuration from given network interface

SYNTAX

```
Remove-AzNetworkInterfaceTapConfig [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] -InputObject
<Microsoft.Azure.Commands.Network.Models.PSNetworkInterfaceTapConfiguration> [-PassThru] [-Confirm] [-WhatIf]
[<CommonParameters>]
```

```
Remove-AzNetworkInterfaceTapConfig [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] -Name
<System.String> -NetworkInterfaceName <System.String> [-PassThru] -ResourceGroupName <System.String>
```

[-Confirm] [-WhatIf] [<CommonParameters>]

Remove-AzNetworkInterfaceTapConfig

[-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]

-ResourceId <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]

DESCRIPTION

The Remove-AzNetworkInterfaceTapConfig cmdlet removes an Azure tap configuration from a network interface list.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Do not ask for confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Network.Models.PSNetworkInterfaceTapConfiguration>

Reference to NetworkInterfaceTapConfig.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Name <System.String>

The virtual network peering name.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-NetworkInterfaceName <System.String>

The virtual network name.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByPropertyName)
Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Returns an object representing the item with which you are working. By default, this cmdlet does not generate any output.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource group name.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-ResourceId <System.String>

NetworkInterfaceTapConfig resource id.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.Network.Models.PSNetworkInterfaceTapConfiguration

OUTPUTS

Microsoft.Azure.Commands.Network.Models.PSNetworkInterface

NOTES

----- Example 1: Remove a tap configuration -----

Remove-AzNetworkInterfaceTapConfig -Name "TapConfiguration" -NetworkInterfaceName "NetworkInterface1"
-ResourceGroupName "ResourceGroup1"

This command removes the TapConfiguration from NetworkInterface1 in a resource group ResourceGroup1. Because the Force parameter is not used, the user will be prompted to confirm this action.

----- Example 2: Remove a network interface -----

```
Get-AzNetworkInterfaceTapConfig -Name "TapConfiguration" -NetworkInterfaceName "NetworkInterface1"
-ResourceGroupName "ResourceGroup1" |
Remove-AzNetworkInterfaceTapConfig -Force
```

This command removes the TapConfiguration from NetworkInterface1 in a resource group ResourceGroup1. Because the Force parameter is used, the user is not prompted for confirmation.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/Remove-aznetworkinterfacetapconfig>

Add-AzNetworkInterfaceTapConfig

Get-AzNetworkInterfaceTapConfig

Set-AzNetworkInterfaceTapConfig