



**Full credit is given to all the above companies including the Operating System that this PDF file was generated!**

### ***Windows PowerShell Get-Help on Cmdlet 'Remove-AzNetworkManagerStaticMember'***

**PS:\*I>Get-HELP Remove-AzNetworkManagerStaticMember -Full***

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

#### **NAME**

Remove-AzNetworkManagerStaticMember

#### **SYNOPSIS**

Removes a network manager static member.

#### **SYNTAX**

Remove-AzNetworkManagerStaticMember            [-AsJob]            [-DefaultProfile

<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force]

-Name <System.String> -NetworkGroupName <System.String> -NetworkManagerName <System.String> [-PassThru]

-ResourceGroupName <System.String> [-Confirm] [-WhatIf]

[<CommonParameters>]

#### **DESCRIPTION**

The Remove-AzNetworkManagerStaticMember cmdlet removes a network manager static member.

## PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Do not ask for confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

The resource name.

Required? true  
Position? named  
Default value None  
Accept pipeline input? True (ByPropertyName)  
Accept wildcard characters? false

-NetworkGroupName <System.String>

The network manager group name.

Required? true  
Position? named  
Default value None  
Accept pipeline input? True (ByPropertyName)  
Accept wildcard characters? true

-NetworkManagerName <System.String>

The network manager name.

Required? true  
Position? named  
Default value None  
Accept pipeline input? True (ByPropertyName)  
Accept wildcard characters? true

-PassThru <System.Management.Automation.SwitchParameter>

{{ Fill PassThru Description }}

Required? false  
Position? named  
Default value False  
Accept pipeline input? False  
Accept wildcard characters? false

-ResourceGroupName <System.String>

The resource group name.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug,

ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see

about\_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

## INPUTS

System.String

## OUTPUTS

System.Boolean

## NOTES

### ----- Example 1 -----

```
Remove-AzNetworkManagerStaticMember -Name "TestStaticMember" -NetworkManagerName "TestNMName"  
-ResourceGroupName "TestRG" -NetworkGroupName "TestNetworkGroup"
```

Removes a network manager static member.

## RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.network/remove-aznetworkmanagerstaticmember>

New-AzNetworkManagerStaticMember

Get-AzNetworkManagerStaticMember