



Windows PowerShell Get-Help on Cmdlet 'Remove-AzNetworkWatcherFlowLog'

PS:\>Get-HELP Remove-AzNetworkWatcherFlowLog -Full

WARNING: The names of some imported commands from the module 'Microsoft.Azure.PowerShell.Cmdlets.Network' include unapproved verbs that might make them less discoverable.

To find the commands with unapproved verbs, run the Import-Module command again with the Verbose parameter. For a list of approved verbs, type Get-Verb.

NAME

Remove-AzNetworkWatcherFlowLog

SYNOPSIS

Deletes the specified flow log resource.

SYNTAX

```

Remove-AzNetworkWatcherFlowLog [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -InputObject
    <Microsoft.Azure.Commands.Network.Models.PSFlowLogResource> [-PassThru] [-Confirm] [-WhatIf]
[<CommonParameters>]

```

```

Remove-AzNetworkWatcherFlowLog [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Location
    <System.String> -Name <System.String> [-PassThru] [-Confirm] [-WhatIf] [<CommonParameters>]

```

```
Remove-AzNetworkWatcherFlowLog [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name
<System.String> -NetworkWatcherName <System.String> [-PassThru] -ResourceGroupName <System.String> [-Confirm]
[-WhatIf] [<CommonParameters>]
```

```
Remove-AzNetworkWatcherFlowLog [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] -Name
<System.String> -NetworkWatcher <Microsoft.Azure.Commands.Network.Models.PSNetworkWatcher> [-PassThru]
[-Confirm] [-WhatIf] [<CommonParameters>]
```

```
Remove-AzNetworkWatcherFlowLog [-AsJob] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-PassThru]
-ResourceId <System.String> [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

Deletes the specified flow log resource.

PARAMETERS

-AsJob <System.Management.Automation.SwitchParameter>

Run cmdlet in the background

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.Network.Models.PSFlowLogResource>

Flow log object.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Location <System.String>

Location of the network watcher.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Name <System.String>

The flow log name.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-NetworkWatcher <Microsoft.Azure.Commands.Network.Models.PSNetworkWatcher>

The network watcher resource.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-NetworkWatcherName <System.String>

The name of network watcher.

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

{{ Fill PassThru Description }}

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-ResourceGroupName <System.String>

The name of the network watcher resource group.

Required? true
Position? named
Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceId <System.String>

Resource ID.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByPropertyName)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable,

OutBuffer, PipelineVariable, and OutVariable. For more information, see [about_CommonParameters \(https://go.microsoft.com/fwlink/?LinkID=113216\)](https://go.microsoft.com/fwlink/?LinkID=113216).

INPUTS

Microsoft.Azure.Commands.Network.Models.PSNetworkWatcher

System.String

Microsoft.Azure.Commands.Network.Models.PSFlowLogResource

OUTPUTS

System.Boolean

NOTES

----- Example 1 -----

Remove-AzNetworkWatcherFlowLog -Location eastus -Name pctest

Online Version: <https://learn.microsoft.com/powershell/module/az.network/remove-aznetworkwatcherflowlog>

New-AzNetworkWatcher

Get-AzNetworkWatcher

Remove-AzNetworkWatcher

Get-AzNetworkWatcherNextHop

Get-AzNetworkWatcherSecurityGroupView

Get-AzNetworkWatcherTopology

Start-AzNetworkWatcherResourceTroubleshooting

New-AzNetworkWatcherPacketCapture

New-AzPacketCaptureFilterConfig

Get-AzNetworkWatcherPacketCapture

Remove-AzNetworkWatcherPacketCapture

Stop-AzNetworkWatcherPacketCapture

New-AzNetworkWatcherProtocolConfiguration

Test-AzNetworkWatcherIPFlow

Test-AzNetworkWatcherConnectivity

Stop-AzNetworkWatcherConnectionMonitor

Start-AzNetworkWatcherConnectionMonitor

Set-AzNetworkWatcherConnectionMonitor

Set-AzNetworkWatcherConfigFlowLog

Remove-AzNetworkWatcherConnectionMonitor

New-AzNetworkWatcherConnectionMonitor

Get-AzNetworkWatcherTroubleshootingResult

Get-AzNetworkWatcherReachabilityReport

Get-AzNetworkWatcherReachabilityProvidersList

Get-AzNetworkWatcherFlowLogStatus

Get-AzNetworkWatcherConnectionMonitorReport

Get-AzNetworkWatcherConnectionMonitor

New-AzNetworkWatcherFlowLog

Set-AzNetworkWatcherFlowLog

Get-AzNetworkWatcherFlowLog

