



Windows PowerShell Get-Help on Cmdlet 'Remove-AzRecoveryServicesAsrStorageClassificationMapping'

PS:\>Get-HELP Remove-AzRecoveryServicesAsrStorageClassificationMapping -Full

NAME

Remove-AzRecoveryServicesAsrStorageClassificationMapping

SYNOPSIS

Deletes the specified ASR storage classification mapping.

SYNTAX

```
Remove-AzRecoveryServicesAsrStorageClassificationMapping [-DefaultProfile  
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>  
-InputObject <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRStorageClassificationMapping>  
[-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Remove-AzRecoveryServicesAsrStorageClassificationMapping cmdlet deletes the specified Azure Site Recovery storage classification mapping.

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-InputObject <Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRStorageClassificationMapping>

The input object to the cmdlet: The ASR storage classification mapping object corresponding to the ASR storage classification mapping to be deleted.

Required? true

Position? named

Default value None

Accept pipeline input? True (ByValue)

Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required? false

Position? named

Default value False
Accept pipeline input? False
Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRStorageClassificationMapping

OUTPUTS

Microsoft.Azure.Commands.RecoveryServices.SiteRecovery.ASRJob

NOTES

----- Example 1 -----

```
$currentJob = Remove-AzRecoveryServicesAsrStorageClassificationMapping -StorageClassificationMapping  
$StorageClassificationMapping
```

Starts the deletion of specified storage classification mapping and returns the ASR job used to track the operation.

RELATED LINKS

Online

Version:

<https://learn.microsoft.com/powershell/module/az.recoveryservices/remove-azrecoveryservicesasrstorageclassificationmapping>

Get-AzRecoveryServicesAsrStorageClassificationMapping

New-AzRecoveryServicesAsrStorageClassificationMapping