



Windows PowerShell Get-Help on Cmdlet 'Remove-AzStorageContainer'

PS:\>Get-HELP Remove-AzStorageContainer -Full

NAME

Remove-AzStorageContainer

SYNOPSIS

Removes the specified storage container.

SYNTAX

```
Remove-AzStorageContainer [-Name] <System.String> [-ClientTimeoutPerRequest <System.Nullable`1[System.Int32]>]
[-ConcurrentTaskCount <System.Nullable`1[System.Int32]>] [-Context <Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext>] [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] [-PassThru]
[-ServerTimeoutPerRequest <System.Nullable`1[System.Int32]>] [-Confirm] [-WhatIf] [<CommonParameters>]
```

DESCRIPTION

The Remove-AzStorageContainer cmdlet removes the specified storage container in Azure.

PARAMETERS

`-ClientTimeoutPerRequest <System.Nullable`1[System.Int32]>`

Specifies the client-side time-out interval, in seconds, for one service request. If the previous call fails in the specified interval, this cmdlet retries the

request. If this cmdlet does not receive a successful response before the interval elapses, this cmdlet returns an error.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

`-ConcurrentTaskCount <System.Nullable`1[System.Int32]>`

Specifies the maximum concurrent network calls. You can use this parameter to limit the concurrency to throttle local CPU and bandwidth usage by specifying the

maximum number of concurrent network calls. The specified value is an absolute count and is not multiplied by the core count. This parameter can help reduce

network connection problems in low bandwidth environments, such as 100 kilobits per second. The default value is 10.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

`-Context <Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext>`

Specifies a context for the container you want to remove. You can use the `New-AzStorageContext` cmdlet to create it.

Required? false

Position? named

Default value None

Accept pipeline input? True (ByPropertyName, ByValue)

Accept wildcard characters? false

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Forces the command to run without asking for user confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the container to remove.

Required? true

Position? 0

Default value None

Accept pipeline input? True (ByPropertyName, ByValue)

Accept wildcard characters? false

-PassThru <System.Management.Automation.SwitchParameter>

Indicates that this cmdlet returns a Boolean that reflects the success of the operation. By default, this cmdlet does not return a value.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-ServerTimeoutPerRequest <System.Nullable`1[System.Int32]>

Specifies the service side time-out interval, in seconds, for a request. If the specified interval elapses before the service processes the request, the storage service returns an error.

Required?	false
Position?	named
Default value	None
Accept pipeline input?	False
Accept wildcard characters?	false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

System.String

Microsoft.Azure.Commands.Common.Authentication.Abstractions.IStorageContext

OUTPUTS

System.Boolean

NOTES

----- Example 1: Remove a container -----

Remove-AzStorageContainer -Name "MyTestContainer"

This example removes a container named MyTestContainer.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.storage/remove-azstoragecontainer>

[Get-AzStorageContainer](#)

[New-AzStorageContainer](#)