



Windows PowerShell Get-Help on Cmdlet 'Remove-AzStorageMover'

PS:\>Get-HELP Remove-AzStorageMover -Full

NAME

Remove-AzStorageMover

SYNOPSIS

Deletes a Storage Mover resource.

SYNTAX

Remove-AzStorageMover -Name <String> -ResourceGroupName <String> [-SubscriptionId <String>] [-DefaultProfile <PSObject>] [-Force] [-AsJob] [-Break]

[-HttpPipelineAppend <SendAsyncStep[]>] [-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-PassThru] [-Proxy <Uri>] [-ProxyCredential <PSCredential>]

[-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm] [<CommonParameters>]

Remove-AzStorageMover -InputObject <IStorageMoverIdentity> [-DefaultProfile <PSObject>] [-Force] [-AsJob] [-Break] [-HttpPipelineAppend <SendAsyncStep[]>]

[-HttpPipelinePrepend <SendAsyncStep[]>] [-NoWait] [-PassThru] [-Proxy <Uri>] [-ProxyCredential <PSCredential>] [-ProxyUseDefaultCredentials] [-WhatIf] [-Confirm]

[<CommonParameters>]

DESCRIPTION

Deletes a Storage Mover resource.

PARAMETERS

-Name <String>

The name of the Storage Mover resource.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-ResourceGroupName <String>

The name of the resource group.

The name is case insensitive.

Required? true

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-SubscriptionId <String>

The ID of the target subscription.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-InputObject <IStorageMoverIdentity>

Identity Parameter

To construct, see NOTES section for INPUTOBJECT properties and create a hash table.

Required? true

Position? named

Default value

Accept pipeline input? true (ByValue)

Accept wildcard characters? false

-DefaultProfile <PSObject>

The credentials, account, tenant, and subscription used for communication with Azure.

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Force [<SwitchParameter>]

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-AsJob [<SwitchParameter>]

Run the command as a job

Required? false

Position? named

Default value False
Accept pipeline input? false
Accept wildcard characters? false

-Break [<SwitchParameter>]

Wait for .NET debugger to attach

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelineAppend <SendAsyncStep[]>

SendAsync Pipeline Steps to be appended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-HttpPipelinePrepend <SendAsyncStep[]>

SendAsync Pipeline Steps to be prepended to the front of the pipeline

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-NoWait [<SwitchParameter>]

Run the command asynchronously

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-PassThru [<SwitchParameter>]

Returns true when the command succeeds

Required? false
Position? named
Default value False
Accept pipeline input? false
Accept wildcard characters? false

-Proxy <Uri>

The URI for the proxy server to use

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyCredential <PSCredential>

Credentials for a proxy server to use for the remote call

Required? false
Position? named
Default value
Accept pipeline input? false
Accept wildcard characters? false

-ProxyUseDefaultCredentials [<SwitchParameter>]

Use the default credentials for the proxy

Required? false

Position? named

Default value False

Accept pipeline input? false

Accept wildcard characters? false

-WhatIf [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

-Confirm [<SwitchParameter>]

Required? false

Position? named

Default value

Accept pipeline input? false

Accept wildcard characters? false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

OUTPUTS

System.Boolean

NOTES

COMPLEX PARAMETER PROPERTIES

To create the parameters described below, construct a hash table containing the appropriate properties. For information on hash tables, run Get-Help about_Hash_Tables.

INPUTOBJECT <IStorageMoverIdentity>: Identity Parameter

[AgentName <String>]: The name of the Agent resource.

[EndpointName <String>]: The name of the Endpoint resource.

[Id <String>]: Resource identity path

[JobDefinitionName <String>]: The name of the Job Definition resource.

[JobRunName <String>]: The name of the Job Run resource.

[ProjectName <String>]: The name of the Project resource.

[ResourceGroupName <String>]: The name of the resource group. The name is case insensitive.

[StorageMoverName <String>]: The name of the Storage Mover resource.

[SubscriptionId <String>]: The ID of the target subscription.

----- EXAMPLE 1 -----

```
PS C:\>Remove-AzStorageMover -ResourceGroupName myResourceGroup -Name myStorageMover
```

RELATED LINKS

<https://learn.microsoft.com/powershell/module/az.storage/move-azstorage>