



Windows PowerShell Get-Help on Cmdlet 'Remove-AzTrafficManagerEndpoint'

PS:\>Get-HELP Remove-AzTrafficManagerEndpoint -Full

NAME

Remove-AzTrafficManagerEndpoint

SYNOPSIS

Removes an endpoint from Traffic Manager.

SYNTAX

```

Remove-AzTrafficManagerEndpoint [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force] -Name
<System.String> -ProfileName <System.String> -ResourceGroupName <System.String> -Type {AzureEndpoints |
ExternalEndpoints | NestedEndpoints} [-Confirm] [-WhatIf]
[<CommonParameters>]

```

```

Remove-AzTrafficManagerEndpoint [-DefaultProfile
<Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>] [-Force]
-TrafficManagerEndpoint <Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerEndpoint> [-Confirm]
[-WhatIf] [<CommonParameters>]

```

DESCRIPTION

The Remove-AzTrafficManagerEndpoint cmdlet removes an endpoint from Azure Traffic Manager.

This cmdlet commits each change to the Traffic Manager service. To remove multiple endpoints from a local Traffic Manager profile object and commit changes in a

single operation, use the Remove-AzTrafficManagerEndpointConfig cmdlet.

You can use the pipeline operator to pass a TrafficManagerEndpoint object to this cmdlet, or you can specify a TrafficManagerEndpoint object by using the

TrafficManagerEndpoint parameter.

Alternatively, you can specify the endpoint name and type by using the Name and Type parameters, together with the ProfileName and ResourceGroupName parameters.

PARAMETERS

-DefaultProfile <Microsoft.Azure.Commands.Common.Authentication.Abstractions.Core.IAzureContextContainer>

The credentials, account, tenant, and subscription used for communication with azure.

Required? false

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-Force <System.Management.Automation.SwitchParameter>

Forces the command to run without asking for user confirmation.

Required? false

Position? named

Default value False

Accept pipeline input? False

Accept wildcard characters? false

-Name <System.String>

Specifies the name of the Traffic Manager endpoint that this cmdlet removes.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ProfileName <System.String>

Specifies the name of a Traffic Manager profile from which this cmdlet removes an endpoint. To obtain a profile, use the Get-AzTrafficManagerProfile cmdlet.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-ResourceGroupName <System.String>

Specifies the name of a resource group. This cmdlet removes a Traffic Manager endpoint from a Traffic Manager profile in the group that this parameter specifies.

Required? true

Position? named

Default value None

Accept pipeline input? False

Accept wildcard characters? false

-TrafficManagerEndpoint <Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerEndpoint>

Specifies the Traffic Manager endpoint that this cmdlet removes. To obtain a TrafficManagerEndpoint object, use the Get-AzTrafficManagerEndpoint cmdlet.

Required? true
Position? named
Default value None
Accept pipeline input? True (ByValue)
Accept wildcard characters? false

-Type <System.String>

Specifies the type of endpoint that this cmdlet adds to the Traffic Manager profile. Valid values are:

- AzureEndpoints

- ExternalEndpoints

- NestedEndpoints

Required? true
Position? named
Default value None
Accept pipeline input? False
Accept wildcard characters? false

-Confirm <System.Management.Automation.SwitchParameter>

Prompts you for confirmation before running the cmdlet.

Required? false
Position? named
Default value False
Accept pipeline input? False
Accept wildcard characters? false

-WhatIf <System.Management.Automation.SwitchParameter>

Shows what would happen if the cmdlet runs. The cmdlet is not run.

Required?	false
Position?	named
Default value	False
Accept pipeline input?	False
Accept wildcard characters?	false

<CommonParameters>

This cmdlet supports the common parameters: Verbose, Debug, ErrorAction, ErrorVariable, WarningAction, WarningVariable, OutBuffer, PipelineVariable, and OutVariable. For more information, see about_CommonParameters (<https://go.microsoft.com/fwlink/?LinkID=113216>).

INPUTS

Microsoft.Azure.Commands.TrafficManager.Models.TrafficManagerEndpoint

OUTPUTS

System.Boolean

NOTES

----- Example 1: Remove an endpoint from a profile -----

```
Remove-AzTrafficManagerEndpoint -Name "contoso" -ProfileName "ContosoProfile" -ResourceGroupName "ResourceGroup11" -Type AzureEndpoints
```

This command removes the Azure endpoint named contoso from the profile named ContosoProfile in the resource group named ResourceGroup11.

RELATED LINKS

Online Version: <https://learn.microsoft.com/powershell/module/az.trafficmanager/remove-aztrafficmanagerendpoint>

Get-AzTrafficManagerEndpoint

Get-AzTrafficManagerProfile

New-AzTrafficManagerEndpoint

Remove-AzTrafficManagerEndpointConfig

Set-AzTrafficManagerProfile